



Getting started with

# **Habari Client for Artemis**

*Version 6.7*

## **LIMITED WARRANTY**

No warranty of any sort, expressed or implied, is provided in connection with the library, including, but not limited to, implied warranties of merchantability or fitness for a particular purpose. Any cost, loss or damage of any sort incurred owing to the malfunction or misuse of the library or the inaccuracy of the documentation or connected with the library in any other way whatsoever is solely the responsibility of the person who incurred the cost, loss or damage. Furthermore, any illegal use of the library is solely the responsibility of the person committing the illegal act.

### **Trademarks**

Habari is a trademark or registered trademark of Michael Justin in Germany and/or other countries. Android is a trademark of Google Inc. Use of this trademark is subject to Google Permissions. The Android robot is reproduced or modified from work created and shared by Google and used according to terms described in the Creative Commons 3.0 Attribution License. Embarcadero, the Embarcadero Technologies logos and all other Embarcadero Technologies product or service names are trademarks, service marks, and/or registered trademarks of Embarcadero Technologies, Inc. and are protected by the laws of the United States and other countries. IBM and WebSphere are trademarks of International Business Machines Corporation in the United States, other countries, or both. HornetQ, WildFly, JBoss and the JBoss logo are registered trademarks or trademarks of Red Hat, Inc. Mac OS is a trademark of Apple Inc., registered in the U.S. and other countries. Oracle, WebLogic and Java are registered trademarks of Oracle and/or its affiliates. Pivotal, RabbitMQ and the RabbitMQ logo are trademarks and/or registered trademarks of GoPivotal, Inc. in the United States and/or other countries. Other brands and their products are trademarks of their respective holders.

**Errors and omissions excepted. Specifications subject to change without notice.**

## Contents

|   |           |
|---|-----------|
| <b>Broker-specific information</b> .....                      | <b>7</b>  |
| <b>Installation</b> .....                                     | <b>8</b>  |
| <b>Requirements</b> .....                                     | <b>8</b>  |
| Development Environment.....                                  | 8         |
| TCP/IP Communication Library.....                             | 8         |
| <b>Installation steps</b> .....                               | <b>8</b>  |
| <b>Simplified API introduced in version 6.0</b> .....         | <b>9</b>  |
| <b>New interface types</b> .....                              | <b>9</b>  |
| <b>IMQContext interface</b> .....                             | <b>9</b>  |
| <b>IMQProducer interface</b> .....                            | <b>9</b>  |
| <b>IMQConsumer interface</b> .....                            | <b>10</b> |
| <b>Source code example</b> .....                              | <b>10</b> |
| <b>Breaking changes in version 6.0</b> .....                  | <b>11</b> |
| <b>Removed conditional symbol HABARI_RAW_TRACE</b> .....      | <b>11</b> |
| <b>Removed support for asynchronous message receive</b> ..... | <b>11</b> |
| <b>Communication Adapters</b> .....                           | <b>12</b> |
| <b>Introduction</b> .....                                     | <b>12</b> |
| Configuration of communication adapters.....                  | 12        |
| Registration of communication adapter class.....              | 12        |
| Available communication adapters.....                         | 13        |
| Limitations of the Synapse communication adapter class.....   | 13        |
| <b>The Programming Model</b> .....                            | <b>14</b> |
| <b>Tutorials</b> .....  | <b>15</b> |
| <b>Quick Start Tutorial</b> .....                             | <b>15</b> |
| Setting up the project.....                                   | 15        |
| Adding code to the project.....                               | 15        |
| Run the demo.....   | 17        |
| Check for memory leaks.....                                   | 17        |
| Tutorial source code.....                                     | 18        |
| <b>Map Message Tutorial</b> .....                             | <b>18</b> |
| Setting up the project.....                                   | 18        |
| Adding code to the project.....                               | 18        |
| Run the demo.....   | 21        |
| Map Message Conversion with Apache ActiveMQ.....              | 21        |
| Tutorial source code.....                                     | 21        |
| <b>Connection Factory</b> .....                               | <b>22</b> |
| <b>Overview</b> .....   | <b>22</b> |
| <b>Creation and configuration</b> .....                       | <b>22</b> |
| <b>Connection URL parameters</b> .....                        | <b>24</b> |
| Heart-beating Support.....                                    | 24        |

|  |           |
|--|-----------|
| TCP Keep-Alive (only supported with Indy).....   | 24        |
| <b>Failover Support.....</b>                     | <b>24</b> |
| Failover Transport Options.....                  | 25        |
| <b>Receipt Support.....</b>                      | <b>26</b> |
| SUBSCRIBE Receipt.....                           | 26        |
| UNSUBSCRIBE Receipt.....                         | 27        |
| SEND Receipt.....                                | 27        |
| DISCONNECT Receipt.....                          | 27        |
| <br>   |           |
| <b>Connections and Sessions.....</b>             | <b>29</b> |
| <b>Connections use Stomp 1.2 by default.....</b> | <b>29</b> |
| <b>Step-by-Step Example.....</b>                 | <b>29</b> |
| Overview.....                                    | 29        |
| Add required units.....                          | 29        |
| Creating a new Connection.....                   | 30        |
| Connection URL Parameters.....                   | 30        |
| Creating a Session.....                          | 30        |
| Using the Session.....                           | 31        |
| Closing a Connection.....                        | 31        |
| <b>Session types overview.....</b>               | <b>31</b> |
| <b>Transacted Sessions.....</b>                  | <b>32</b> |
| Create a transacted session.....                 | 32        |
| Send messages.....                               | 33        |
| Committing a transaction.....                    | 33        |
| Rolling back a transaction.....                  | 33        |
| Transacted message acknowledgement.....          | 34        |
| <br>   |           |
| <b>Destinations.....</b>                         | <b>35</b> |
| <b>Introduction.....</b>                         | <b>35</b> |
| <b>Create a new Destination.....</b>             | <b>35</b> |
| Queues.....                                      | 35        |
| Topics.....                                      | 36        |
| <br>   |           |
| <b>Producer and Consumer.....</b>                | <b>37</b> |
| <b>Message Producer.....</b>                     | <b>37</b> |
| Persistent messages.....                         | 37        |
| <b>Message Consumer.....</b>                     | <b>38</b> |
| Message Selector.....                            | 38        |
| <b>Synchronous Receive.....</b>                  | <b>38</b> |
| <br>   |           |
| <b>Durable Subscriptions.....</b>                | <b>40</b> |
| <b>Description.....</b>                          | <b>40</b> |
| Creation.....                                    | 40        |
| <br>   |           |
| <b>Temporary Queues.....</b>                     | <b>41</b> |
| <b>Introduction.....</b>                         | <b>41</b> |
| Library Support.....                             | 41        |
| Resource Management.....                         | 41        |

|   |           |
|---|-----------|
| <b>Message Options</b> .....                  | <b>42</b> |
| <b>Standard Properties</b> .....              | <b>42</b> |
| Properties for outgoing messages.....         | 42        |
| Properties for incoming messages.....         | 42        |
| <b>Reserved property names</b> .....          | <b>43</b> |
| Examples.....                                 | 43        |
| Prefix for custom headers.....                | 44        |
| <b>Selectors</b> .....                        | <b>44</b> |
| Supported message brokers.....                | 44        |
| <br>  |           |
| <b>Object Messages</b> .....                  | <b>45</b> |
| <b>Introduction</b> .....                     | <b>45</b> |
| Object Serialization.....                     | 45        |
| <b>Message Transformers</b> .....             | <b>45</b> |
| Memory Management.....                        | 45        |
| Assign a Message Transformer.....             | 46        |
| Create and Send an ObjectMessage.....         | 46        |
| Complete Example using NativeXml.....         | 47        |
| <br>  |           |
| <b>Stomp 1.2</b> .....                        | <b>49</b> |
| <b>Connection configuration</b> .....         | <b>49</b> |
| Specification.....                            | 50        |
| <b>Sending heart-beat signals</b> .....       | <b>50</b> |
| <b>Checking for incoming heartbeats</b> ..... | <b>51</b> |
| <b>Reading server-side heartbeats</b> .....   | <b>51</b> |
| <br>  |           |
| <b>Example Applications</b> .....             | <b>52</b> |
| <b>Shared units for demo projects</b> .....   | <b>53</b> |
| <b>ConsumerTool</b> .....                     | <b>54</b> |
| Examples.....                                 | 55        |
| <b>ProducerTool</b> .....                     | <b>56</b> |
| Examples.....                                 | 56        |
| <b>Performance test</b> .....                 | <b>58</b> |
| <b>Throughput test</b> .....                  | <b>60</b> |
| Examples.....                                 | 60        |
| <br>  |           |
| <b>Unit Tests</b> .....                       | <b>61</b> |
| <b>Introduction</b> .....                     | <b>61</b> |
| <b>Test project configuration</b> .....       | <b>61</b> |
| Logging.....                                  | 61        |
| Raw message logging.....                      | 61        |
| Optional units.....                           | 61        |
| Synapse communication adapter.....            | 61        |
| <b>Test units</b> .....                       | <b>61</b> |
| <b>Test execution</b> .....                   | <b>62</b> |
| Requirements.....                             | 62        |
| Test destinations.....                        | 62        |
| <b>STOMP 1.2</b> .....                        | <b>63</b> |

|   |           |
|---|-----------|
| <b>Logging with SLF4P</b> .....   | <b>64</b> |
| <b>Introduction</b> .....   | <b>64</b> |
| <b>IDE and project configuration</b> .....                              | <b>64</b> |
| Delphi.....   | 64        |
| Lazarus.....  | 64        |
| <b>LoggingHelper unit</b> .....   | <b>64</b> |
| <br>  |           |
| <b>Conditional Symbols</b> .....  | <b>66</b> |
| <b>Caution</b> .....  | <b>66</b> |
| <b>Conditional symbols for release builds</b> .....                     | <b>66</b> |
| HABARI_ALLOW_UNKNOWN_URL_PARAMS.....                                    | 66        |
| HABARI_LOGGING.....   | 66        |
| HABARI_SSL_SUPPORT.....   | 66        |
| HABARI_TCP_KEEPALIVE.....   | 67        |
| HABARI_USE_INTERCEPT.....   | 67        |
| <b>Conditional symbols for unit test projects</b> .....                 | <b>67</b> |
| HABARI_TEST_OPTIONAL_UNITS.....   | 67        |
| HABARI_TEST_SYNAPSE.....  | 67        |
| HABARI_TEST_USE_MGMT_API.....   | 67        |
| <br>  |           |
| <b>SSL/TLS Support</b> .....  | <b>69</b> |
| <b>SSL communication adapter classes</b> .....                          | <b>69</b> |
| Mixed Use.....  | 69        |
| SSL configuration.....  | 69        |
| <b>Indy SSL Demo</b> .....  | <b>69</b> |
| Notes.....  | 70        |
| Example output.....   | 70        |
| <b>Support</b> .....  | <b>71</b> |
| <br>  |           |
| <b>Useful Units</b> .....   | <b>72</b> |
| <b>BTStreamHelper unit</b> .....  | <b>72</b> |
| <b>BTJavaPlatform unit</b> .....  | <b>72</b> |
| <br>  |           |
| <b>Library Limitations</b> .....  | <b>73</b> |
| <b>MessageConsumer</b> .....  | <b>73</b> |
| How do I implement synchronous receive from multiple destinations?..... | 73        |
| <b>Message properties</b> .....   | <b>73</b> |
| Only string data type supported by Stomp.....                           | 73        |
| <b>Multi threading</b> .....  | <b>73</b> |
| <b>Free Pascal specific restrictions</b> .....                          | <b>74</b> |
| <b>Broker-specific limitations</b> .....                                | <b>74</b> |
| Transacted Sessions.....  | 74        |
| Other broker specific limitations.....                                  | 74        |
| <br>  |           |
| <b>Frequently Asked Questions</b> .....                                 | <b>75</b> |
| <b>Technical questions</b> .....  | <b>75</b> |
| Why am I getting 'undeclared identifier IndyTextEncoding_UTF8'?.....    | 75        |
| Why am I getting 'Undeclared identifier: 'TimeSeparator'?'.....         | 75        |
| Why am I getting 'Found no matching consumer' errors?.....              | 75        |

|   |           |
|---|-----------|
| <b>Online Resources.....</b>                              | <b>77</b> |
| <b>Third-party libraries.....</b>                         | <b>77</b> |
| Indy.....   | 77        |
| SLF4P.....  | 77        |
| JsonDataObjects.....                                      | 77        |
| Synapse.....  | 77        |
| <b>Specifications.....</b>                                | <b>78</b> |
| <b>Online articles.....</b>                               | <b>78</b> |
| <b>Online Videos.....</b>                                 | <b>79</b> |
| <br>  |           |
| <b>Support.....</b>                                       | <b>80</b> |
| <b>Bug reports and support inquiries.....</b>             | <b>80</b> |
| Advanced support.....                                     | 80        |
| <br>  |           |
| <b>Broker-specific notes.....</b>                         | <b>81</b> |
| <b>Broker configuration.....</b>                          | <b>81</b> |
| Reference.....  | 81        |
| <br>  |           |
| <b>Quick start guide for Apache ActiveMQ Artemis.....</b> | <b>82</b> |
| <b>Installation.....</b>                                  | <b>82</b> |
| <br>  |           |
| <b>Index.....</b>   | <b>83</b> |

---

## Broker-specific information

For broker-specific notes, please read chapter Broker-specific notes on page 81 ff. and Quick start guide for Apache ActiveMQ Artemis on page 82.

## Installation

---

### Requirements

#### Development Environment

- **Embarcadero Delphi** 2009 Update 4 or higher
- or -
- **Free Pascal** 3.0.4 or higher

**Lazarus** 1.8 or newer is required to run the **FPCUnit** test suite. The DUnit test suite and the GUI demo applications require Delphi 2009 for compilation.

#### TCP/IP Communication Library

- **Internet Direct (Indy) 10.6** (recommended)
- or -
- **Synapse** Release 40<sup>1</sup>

---

### Installation steps

The installer application will guide you through the installation process.

By default Habari Client for Artemis will be installed in the folder

C:\Users\Public\Documents\Habarisoft\habari-artemis-6.7

1 Only release 40 of Ararat Synapse is used for Habari Client library development and tests



## Simplified API introduced in version 6.0

---

### New interface types

The new API in Habari Client libraries 6.0 is based on three new interfaces which reduce the amount of client code:

- IMQContext
- IMQProducer
- IMQConsumer

---

### IMQContext interface

A IMQContext object encapsulates both the IConnection and the ISession object of the classic API. The connection factory interface contains new methods to create IMQContext objects:

#### Code example

```
function CreateContext: IMQContext; overload;  
function CreateContext(const AcknowledgeMode:  
    TAcknowledgementMode): IMQContext; overload;  
function CreateContext(const Username, Password: string):  
    IMQContext; overload;  
function CreateContext(const Username, Password: string;  
    const AcknowledgeMode: TAcknowledgementMode):  
    IMQContext; overload;
```

The IMQContext provides methods to create messages, producer and consumer objects, destinations (queues, topics, temporary queues, temporary topics, durable subscribers and so forth), and for transaction control (commit, rollback).

---

### IMQProducer interface

A IMQProducer object provides methods to produce and send messages to the broker. As a shortcut, a method allows to send text or bytes messages without creating IMessage or IBytesMessage object by providing the text or bytes as a parameter.

Code example

```
function Send(const Destination: IDestination;
              const Body: string): IMQProducer; overload;
function Send(const Destination: IDestination;
              const AMessage: IMessage): IMQProducer; overload;
```

---

## IMQConsumer interface

An IMQConsumer object provides methods to consume messages from the broker.

The following example is taken from the unit tests. It uses the new API to create and send a text message to a broker queue destination, and then receives the message from this queue.

---

## Source code example

Code example

```
procedure TNewApiTests.TestSendMessage;
var
  Context: IMQContext;
  Destination: IQueue;
  Producer: IMQProducer;
  Consumer: IMQConsumer;
  TextMessage: ITextMessage;
begin
  Context := Factory.CreateContext;
  Destination := Context.CreateQueue(GetQueueName);

  Producer := Context.CreateProducer;
  Producer.Send(Destination, 'Hello World');

  Consumer := Context.CreateConsumer(Destination);
  TextMessage := Consumer.Receive(2500) as ITextMessage;

  CheckEquals('Hello World', TextMessage.Text);
  Context.Close;
end;
```

## Breaking changes in version 6.0

---

### Removed conditional symbol HABARI\_RAW\_TRACE

For detailed logging of network traffic, you may use the conditional symbol HABARI\_USE\_INTERCEPT.

---

### Removed support for asynchronous message receive

The following methods and properties are no longer available:

```
function CreateConsumer(const Destination: IDestination;  
    const MessageSelector: string; const NoLocal: Boolean;  
    const MessageListener: IMessageListener): IMessageConsumer;
```

```
IMessageConsumer = interface  
    ...  
    function GetMessageListener: IMessageListener;  
    procedure SetMessageListener(const Value: IMessageListener);  
  
    property MessageListener: IMessageListener read GetMessageListener write  
        SetMessageListener;  
    ...
```

## Communication Adapters

---

### Introduction

Habari Client for Artemis uses communication adapters as an abstraction layer for the TCP/IP library. All connections create their own internal instance of the adapter class.

### Configuration of communication adapters

No configuration is required for the communication adapters. Applications specify communication and connection options in URL parameters or connection class properties or connection factory settings.

### Registration of communication adapter class

A communication adapter implementation can be prepared for usage by simply adding its Delphi unit to the project.

#### Code example

```
program ClientUsingIndy;  
  
uses  
  BCommAdapterIndy, // use Internet Direct (Indy)  
  BTConnectionFactory, BTJMSInterfaces,  
  SysUtils;  
...
```

Behind the scenes, the communication adapter class will register itself with the communication adapter manager in the BTAdapterRegistry unit.

### Default adapter class

Applications typically use only one of the available communication adapter classes for all connections.

The library allows to register two or more adapter classes and switch at run-time, using methods in the adapter registry in unit BTAdapterRegistry - this feature is mainly for tests and demonstration purposes.

If more than one communication adapter is in the project, the **first** adapter class in the list will be the default adapter class. Example:

## Code example

```

program ClientUsingIndyOrSynapse;

uses
  BTCommAdapterIndy, // use Internet Direct (Indy) as default adapter class
  BTCommAdapterSynapse, // and register the Synapse adapter class
  BTConnectionFactory, BTJMSInterfaces,
  SysUtils;
...

```

The default adapter class can be changed at run-time by setting the adapter class either by its name or by its class type.

## Available communication adapters

The library includes two adapter classes for TCP/IP libraries, one for Indy (Internet Direct) and one for Synapse.

| Adapter Class         | Unit                 |
|-----------------------|----------------------|
| TBTCommAdapterIndy    | BTCommAdapterIndy    |
| TBTCommAdapterSynapse | BTCommAdapterSynapse |

Table 1: Communication Adapters

## Limitations of the Synapse communication adapter class

- The Synapse library does not support the `ConnectTimeout` property in synchronous socket operation mode, as connect timeouts are handled by the operating system. Indy uses a background thread to abort the connect operation.<sup>2</sup>
- Release 40 of Ararat Synapse is used for Habari Client library development and tests. This is the last announced release, dated April 24, 2012. This release is compatible for Delphi versions before XE4<sup>3</sup>. If you use a newer release of Ararat Synapse, please let me know if you encounter any API incompatibilities or other problems.

<sup>2</sup> <http://www.ararat.cz/synapse/doku.php/public:howto:connecttimeout>

<sup>3</sup> [http://docwiki.embarcadero.com/RADStudio/XE4/en/Global\\_Variables](http://docwiki.embarcadero.com/RADStudio/XE4/en/Global_Variables)

## The Programming Model

Habari Client libraries use a programming model which is based on message producers and message consumers, sessions, connections and connection factories.

The basic API is the same for all library versions to allow easy migration between supported message brokers (with the exception of broker-specific features).




Illustration 1: Programming Model

# Tutorials

---

## Quick Start Tutorial

This tutorial provides a very simple and quick introduction to Habari Client for Artemis by walking you through the creation of a simple "Hello World" application. Once you are done with this tutorial, you will have a general knowledge of how to create and run Habari applications.

This tutorial takes less than 10 minutes to complete.

### Setting up the project

To create a new project:

1. Start the Delphi IDE.
2. In the IDE, choose File > New > VCL Forms Application – Delphi
3. Choose Project > Options ... to open the Project Options dialog
4. In the options tree on the left, select 'Delphi Compiler'
5. Add the source directory of Habari Client for Artemis and the Indy source directories to the 'Search path'
6. Choose Ok to close the Project Options dialog
7. Save the project as HelloMQ

Now the project is created and saved.

You should see the main form in the GUI designer now.

### Adding code to the project

To use the Habari Client for Artemis library, you need to add the required units to the source code.

8. Switch to Code view (F12)
9. Add the required units to the interface uses list:

#### Code example

```
uses  
  BTConnectionFactory,  
  BTJMSInterfaces,
```

## 16 Habari Client for Artemis 6.7

```
BTCommAdapterIndy,  
// auto-generated unit references  
Windows, Messages, SysUtils, ...
```

10. Compile and save the project.
11. Switch to Design view (F12), go to the Tool palette (Ctrl+Alt+P) and select TButton, add a Button to the form.
12. Double click on the new button to jump to the Button Click handler
13. Add the following code to send the message:

### Code example

```
procedure TForm1.Button1Click(Sender: TObject);  
var  
    Factory: IConnectionFactory;  
    Connection: IConnection;  
    Session: ISession;  
    Destination: IDestination;  
    Producer: IMessageProducer;  
begin  
    Factory := TBTConnectionFactory.Create('stomp://localhost');  
    Connection := Factory.CreateConnection;  
    Connection.Start;  
  
    Session := Connection.CreateSession(False, amAutoAcknowledge);  
    Destination := Session.CreateQueue('HelloMQ');  
    Producer := Session.CreateProducer(Destination);  
    Producer.Send(Session.CreateTextMessage('Hello world!'));  
  
    Connection.Close;  
end;
```

14. Add a second button and double click on the new button to jump to the Button Click handler
15. Add the following code to receive and display the message:

### Code example

```
procedure TForm1.Button2Click(Sender: TObject);  
var  
    Factory: IConnectionFactory;  
    Connection: IConnection;  
    Session: ISession;  
    Destination: IDestination;
```



```

Consumer: IMessageConsumer;
Msg: IMessage;
begin
  Factory := TBTConnectionFactory.Create('stomp://localhost');
  Connection := Factory.CreateConnection;
  Connection.Start;

  Session := Connection.CreateSession(False, amAutoAcknowledge);
  Destination := Session.CreateQueue('HelloMQ');
  Consumer := Session.CreateConsumer(Destination);
  Msg := Consumer.Receive(1000) as IMessage;

  if Assigned(Msg) then
    ShowMessage(Msg.Text)
  else
    ShowMessage('Error: no message received');

  Connection.Close;
end;

```

16. Compile and save the project

## Run the demo

- Launch the message broker
- Start the application
- Click on Button 1 to send the message to the queue
- Click on Button 2 to receive the message and display it

You can run two instances of the application at the same time, and also on different computers if the IP address of the message broker is used instead of localhost.

## Check for memory leaks

To verify that the program does not cause memory leaks, insert a line in the project file HelloMQ.dpr:

### Code example

```

program HelloMQ;

uses
  Forms,
  Unit1 in 'Unit1.pas' {Form1};

{$R *.res}

```

```
begin
  ReportMemoryLeaksOnShutdown := True; // check for memory leaks
  Application.Initialize;
  Application.MainFormOnTaskbar := True;
  Application.CreateForm(TForm1, Form1);
  Application.Run;
end.
```

## Tutorial source code

The tutorial source code is included in the demo folder. It does not include a .proj file so you still need to add the Habari and Indy source paths to the project options.

---

## Map Message Tutorial

This tutorial provides a quick introduction to Habari Client for Artemis by walking you through the creation of a simple map message exchange application.

This tutorial takes less than 10 minutes to complete.

## Setting up the project

To create a new project:

1. Start the Delphi IDE.
2. In the IDE, choose File > New > VCL Forms Application – Delphi
3. Choose Project > Options ... to open the Project Options dialog
4. In the options tree on the left, select 'Delphi Compiler'
5. Add the source directory of Habari source, the Habari source\optional, and the Indy source directories to the 'Search path'
6. Choose OK to close the Project Options dialog
7. Save the project as HelloMapMessage

Now the project is created and saved.

You should see the main form in the GUI designer now.

## Adding code to the project

To use the Habari Client for Artemis library, you need to add the required units to the source code.

8. Switch to Code view (F12)
9. Add the required units to the interface uses list:

## Code example

```

uses
  BTConnectionFactory, BTJMSInterfaces, BTCommAdapterIndy, BTConnection,
  BTMessageTransformerXMLMapDocument, BTSerialIntf, BTTypes,
  // auto-generated unit references
  Windows, Messages, SysUtils, ...

```

10. Compile and save the project.

11. Switch to Design view (F12), go to the Tool palette (Ctrl+Alt+P) and add a TMemo and a TButton to the form.

12. Double click on the new button to jump to the Button Click handler

13. Add the following code to send the message:

## Code example

```

procedure TForm1.Button1Click(Sender: TObject);
var
  Factory: IConnectionFactory;
  Connection: IConnection;
  Session: ISession;
  Destination: IDestination;
  Producer: IMessageProducer;
  MapMessage: IMapMessage;
  Key: string;
begin
  Factory := TBConnectionFactory.Create('stomp://localhost');
  Connection := Factory.CreateConnection;
  SetTransformer(Connection, TBMessageTransformerXMLMapDocument.Create(nil));
  Connection.Start;

  Session := Connection.CreateSession(False, amAutoAcknowledge);
  Destination := Session.CreateQueue('HelloMapMessage');
  Producer := Session.CreateProducer(Destination);

  MapMessage := Session.CreateMapMessage;
  MapMessage.SetString('DateTimeToStr(Now)', DateTimeToStr(Now));
  MapMessage.SetString('ParamStr(0)', ParamStr(0));

  Producer.Send(MapMessage);

  Mem1.Lines.Append('Sent:');
  for Key in MapMessage.GetMapNames do
  begin
    Mem1.Lines.Append(Key + '=' + MapMessage.GetString(Key));
  end;

```

```
Connection.Close;
end;
```

14. Add a second button and double click on the new button to jump to the Button Click handler

15. Add the following code to receive and display the message:

#### Code example

```
procedure TForm1.Button2Click(Sender: TObject);
var
  Factory: IConnectionFactory;
  Connection: IConnection;
  Session: ISession;
  Destination: IDestination;
  Consumer: IMessageConsumer;
  MapMessage: IMapMessage;
  Key: string;
begin
  Factory := TBTConnectionFactory.Create('stomp://localhost');
  Connection := Factory.CreateConnection;
  SetTransformer(Connection, TBTMessageTransformerXMLMapDocument.Create(nil));
  Connection.Start;

  Session := Connection.CreateSession(False, amAutoAcknowledge);
  Destination := Session.CreateQueue('HelloMapMessage'
    + '?transformation=' + BTSerialIntf.TRANSFORMER_ID_MAP_XML);
  Consumer := Session.CreateConsumer(Destination);

  MapMessage := Consumer.Receive(1000) as IMapMessage;

  if Assigned(MapMessage) then
  begin
    Mem1.Lines.Append('Received: ');
    for Key in MapMessage.GetMapNames do
    begin
      Mem1.Lines.Append(Key + '=' + MapMessage.GetString(Key));
    end;
  end;

  Connection.Close;
end;
```

16. Compile and save the project

## Run the demo

- Launch the message broker
- Start the application
- Click on Button 1 to send the map message to the queue
- Click on Button 2 to receive the map message and display it

You can run two instances of the application at the same time, and also on different computers if the IP address of the message broker is used instead of localhost.

## Map Message Conversion with Apache ActiveMQ

Note: if you send and receive map messages using the library, message brokers will receive them as simple STOMP text messages with a special header property "transformation" which is set to the value JMS\_MAP\_XML (or JMS\_MAP\_JSON if you use a JSON based map transformer class).

Most message brokers will not perform any special processing of these STOMP messages. A notable exception is Apache ActiveMQ: if the broker receives a STOMP message with the JMS\_MAP\_XML or JMS\_MAP\_JSON transformation header, it will convert the message internally to a 'native' JMS MapMessage. This allows Java clients to receive the message sent from the Delphi application as a MapMessage without the need to parse a XML body.

Habari Client map message transformers only support string properties.

## Tutorial source code

The tutorial source code is included in the demo folder. It does not include a .proj file so you still need to add the Habari and Indy source paths to the project options.

## Connection Factory

---

### Overview

A connection factory is an object which holds all information required for the creation of a connection objects.

A factory instance is created and configured only once. It then may be used to create actual connection objects when needed. For example, a worker thread may create the connection factory once at program start-up and use it to create a new connection object whenever a connection failure occurred.

---

### Creation and configuration

The code example below shows a helper function which creates a connection factory, and returns it using the interface type `IConnectionFactory`.

The factory will be freed automatically when there are no more references to it.

#### Code example

```
function TExample.CreateConfiguredFactory: IConnectionFactory;
var
  Factory: IConnectionFactory;
begin
  // -----
  // create an instance
  // -----
  Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?
send.receipt=true');

  // -----
  // return the instance
  // -----
  Result := Factory;
end;
```

This code example is useful for most simple client applications. However, because the local factory variable is declared as `IConnectionFactory`, advanced configuration properties in the class `TBTConnectionFactory` such as `ClientID` and `SendTimeout` are not accessible.

To access them, declare the local factory with the class type as shown in the next example:

## Code example

```

function TExample.CreateConfiguredFactory: IConnectionFactory;
var
  Factory: TBTConnectionFactory;
begin
  // -----
  // create and assign to local variable
  // -----
  Factory := TBTConnectionFactory.Create;

  // -----
  // additional configuration
  // -----

  Factory.BrokerURL := 'broker.example.com';
  Factory.UserName := 'guest';
  Factory.Password := 'guest';
  Factory.ClientID := 'myclientId';
  Factory.SendTimeout := 10000;
  Factory.ConnectTimeout := 10000; // Indy only

  // -----
  // return the configured factory
  // -----
  Result := Factory;
end;

```

Warning: if the method signature is changed to return the class TBTConnectionFactory instead, a memory leak will occur.

## Code example

```

function TExample.Run;
var
  F: IConnectionFactory;
  C: IConnection;
begin
  // -----
  // get a factory and use it to create a connection object
  // -----
  F := CreateConfiguredFactory;

  C := F.CreateConnection;

  // -----
  // start and use the connection
  // -----
  C.Start;

```

```

...
// -----
// close the connection
// -----
C.Close;
end;

```

---

## Connection URL parameters

### Heart-beating Support

STOMP 1.1 introduced heart-beating, its configuration is covered in the chapter Stomp 1.2

### TCP Keep-Alive (only supported with Indy)

The library supports TCP keep-alive with an optional connection URL parameter, `tcp.keepalive`.

The parameter takes two arguments. On Linux, the first argument is the initial delay before the first keep-alive, the second argument specifies the interval (both values are in milliseconds). On the Windows platform, the values of these arguments are ignored and the operating system uses default values for initial delay<sup>4</sup> and interval<sup>5</sup>, which can be modified in the registry.

#### Code example

```

Factory := TBTCConnectionFactory.Create('user', 'password', 'stomp://localhost?
tcp.keepalive=1000,1000');

```

|           |  |
|-----------|--|
| Note      | TCP keep-alive is currently only supported by the Indy communication adapter   |
| Important | To enable TCP keep-alive, the project must be compiled with the conditional symbol <code>HABARI_TCP_KEEPALIVE</code> |

---

## Failover Support

The Failover transport layers reconnect logic on top of the Stomp transport.<sup>6</sup>

4 <http://technet.microsoft.com/en-us/library/cc957549.aspx>

5 <http://technet.microsoft.com/en-us/library/cc957548.aspx>

6 <http://activemq.apache.org/failover-transport-reference.html>



The Failover configuration syntax allows you to specify any number of composite URIs. The Failover transport randomly chooses one of the composite URI and attempts to establish a connection to it. If it does not succeed, a new connection is established to one of the other URIs in the list.

Example for a failover URI:

```
failover:(stomp://primary:61613,stomp://secondary:61613)
```

## Failover Transport Options

| Option Name           | Default Value | Description   |
|-----------------------|---------------|---|
| initialReconnectDelay | 10            | How long to wait before the first reconnect attempt (in ms)   |
| maxReconnectDelay     | 30000         | The maximum amount of time we ever wait between reconnect attempts (in ms)  |
| backOffMultiplier     | 2.0           | The exponent used in the exponential backoff attempts   |
| maxReconnectAttempts  | -1            | -1 is default and means retry forever, 0 means don't retry (only try connection once but no retry)<br>If set to > 0, then this is the maximum number of reconnect attempts before an error is sent back to the client |
| randomize             | true          | use a random algorithm to choose the the URI to use for reconnect from the list provided  |

Table 2: Failover Transport Options

Example URI:

```
failover:(stomp://localhost:61616,stomp://remotehost:61616)?initialReconnectDelay=100&maxReconnectAttempts=10
```

### Code example

```
Factory := TBTConnectionFactory.Create('failover:(stomp://primary:61616,stomp://localhost:61613)?maxReconnectAttempts=3&randomize=false') do
try
```

```

Conn := Factory.CreateConnection;
Conn.Start;
...
Conn.Stop;
finally
  Conn.Close;
end;

```

## Receipt Support

The STOMP standard supports receipt messages since version 1.0:

"Any client frame other than CONNECT may specify a *receipt* header with an arbitrary value. This will cause the server to acknowledge receipt of the frame with a RECEIPT frame which contains the value of this header as the value of the *receipt-id* header in the RECEIPT packet."<sup>789</sup>

With Habari Client for Artemis, client applications may configure receipt headers for the frame types listed below.

After the STOMP frame has been sent to the broker, the client library waits for the RECEIPT frame for a defined time, which may be configured per frame type. If the broker does not send a receipt within the time-out interval, the client library will raise an exception. If the client receives a receipt with the wrong receipt-id header, it will raise an exception.

### Receipt Support Parameters

| STOMP frame | Parameter           | Example URL                                    |
|-------------|---------------------|--|
| SUBSCRIBE   | subscribe.receipt   | stomp://localhost?subscribe.receipt=true       |
| UNSUBSCRIBE | unsubscribe.receipt | stomp://localhost?<br>unsubscribe.receipt=true |
| SEND        | send.receipt        | stomp://localhost?send.receipt=true            |
| DISCONNECT  | disconnect.receipt  | stomp://localhost?disconnect.receipt=tru       |

### SUBSCRIBE Receipt

To request server receipts for SUBSCRIBE frames, use the optional connection URL parameter, `subscribe.receipt`.

7 <https://stomp.github.io/stomp-specification-1.0.html>

8 [https://stomp.github.io/stomp-specification-1.1.html#Header\\_receipt](https://stomp.github.io/stomp-specification-1.1.html#Header_receipt)

9 [https://stomp.github.io/stomp-specification-1.2.html#Header\\_receipt](https://stomp.github.io/stomp-specification-1.2.html#Header_receipt)

**Code example**

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?
subscribe.receipt=true');
```

If the broker does not send a receipt within the time-out interval, the client library will raise an exception.

**UNSUBSCRIBE Receipt**

To request server receipts for UNSUBSCRIBE frames, use the optional connection URL parameter, `unsubscribe.receipt`.

**Code example**

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?
unsubscribe.receipt=true');
```

If the broker does not send a receipt within the time-out interval, the client library will raise an exception.

**SEND Receipt**

To request server receipts for SEND frames, use the optional connection URL parameter, `send.receipt`.

**Code example**

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?
send.receipt=true');
```

If the broker does not send a receipt within the time-out interval, the client library will raise an exception.

Note: for additional reliability, the client can use transactional send (see section "Transacted Sessions").

**DISCONNECT Receipt**

To request server receipts for DISCONNECT frames, use the optional connection URL parameter, `disconnect.receipt`.

Code example

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?  
disconnectreceipt=true');
```

Without this parameter, the client will disconnect the socket connection immediately after sending the DISCONNECT frame to the broker.

With `disconnectreceipt=true`, the client will send the DISCONNECT frame and then wait for the broker receipt frame. If the broker does not answer, the client library will raise an exception. The client application should treat its messages as undelivered.

Note: for additional reliability, the client can use transactional send (see section "Transacted Sessions"), and message receipts (see section "SEND Receipt").

# Connections and Sessions

---

## Connections use Stomp 1.2 by default

Connections use Stomp 1.2 by default since

- Habari Client for Apache ActiveMQ 5.1
- Habari Client for Apache Artemis 5.1
- Habari Client for RabbitMQ 5.1

With OpenMQ, the library still uses Stomp 1.0.

Stomp version may be specified by connection URL parameters. The default protocol version is defined in the BTBrokerConsts unit.

---

## Step-by-Step Example

### Overview

This example will send a single message to a destination queue (ExampleQueue).<sup>10</sup>

### Add required units

Three units are required for this example

- a communication adapter unit (e. g. BTCommAdapterIndy)
- a connection factory unit (BTConnectionFactory)
- the unit containing the interface declarations (BTJMSInterfaces)

The SysUtils unit is necessary for the exception handling.

#### Code example

```
program SendOneMessage;  
  
{$APPTYPE CONSOLE}  
  
uses
```

<sup>10</sup>Compatibility note: non-existing queues are created automatically by the broker – with the exception of Artemis and HornetQ which require them to be configured before usage

```

BTCommAdapterIndy,
BTConnectionFactory,
BTJMSInterfaces,
SysUtils;
...

```

## Creating a new Connection

New connections are created by calling the `CreateConnection` method of a connection factory.

### Code example

```

var
  Factory: IConnectionFactory;
  Connection: IConnection;
  ...
begin
  Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost');
  Connection := Factory.CreateConnection;
  ...

```

- For connection factory creation and configuration options please see chapter "[Creation and configuration](#)".
- Since `IConnection` is an interface type, the connection instance will be destroyed automatically if there are no more references to it in the program.

## Connection URL Parameters

Connection URL parameters are documented in chapter "[Connection URL parameters](#)" and in chapter "Stomp 1.2".

## Creating a Session

To create the communication session,

- declare a variable of type `ISession`
- use the helper method `CreateSession` of the connection, and specify the acknowledgment mode

Please check the API documentation for the different session types and acknowledgement modes.

Since `ISession` is an interface type, the session instance will be destroyed automatically if there are no more references to it in the program.

## Code example

```
Session := Connection.CreateSession(False, amAutoAcknowledge);
```

## Using the Session

The Session variable is ready to use now. Destinations, producers and consumers will be covered in the next chapters.

## Code example

```
Destination := Session.CreateQueue('ExampleQueue');
Producer := Session.CreateProducer(Destination);
Producer.Send(Session.CreateTextMessage('This is a test message'));
```

## Closing a Connection

Finally, the application closes the connection. The client will disconnect from the message broker. Closing a connection also implicitly closes all open sessions.

## Code example

```
finally
    Connection.Close;
end;
end.
```

Note: Close will be called automatically if the connection is destroyed. But because unclosed connections use resources, Close should be called when the connection is no longer needed. When logging is enabled, the connection class will also log a message when a connection is destroyed without calling Close.

---

## Session types overview

The table below shows the supported parameter combinations for the Connection.CreateSession method and their effect on the session transaction and acknowledgment features.

| Parameters                                | Client MUST acknowledge message receipt <sup>11</sup> | Transaction support for |     | STOMP Version |
|---|---|-------------------------|-----|---------------|
|   |   | Send                    | Ack |               |
| CreateSession(False, amAutoAcknowledge)   | No  | -                       | -   | 1.0           |
| CreateSession(False, amClientAcknowledge) | Yes (cumulative effect)                               | -                       | -   | 1.0           |
| CreateSession(False, amClientIndividual)  | Yes   | -                       | -   | 1.2           |
| CreateSession(True, amAutoAcknowledge)    | No  | ✓                       | -   | 1.0           |
| CreateSession(True, amClientAcknowledge)  | Yes (cumulative effect)                               | ✓                       | ✓ ① | 1.0           |
| CreateSession(True, amClientIndividual)   | Yes   | ✓                       | ✓ ① | 1.2           |
| CreateSession(True, amTransactional)      | No  | ✓                       | -   | 1.0           |

Table 3: Session creation parameters

① – not supported by ActiveMQ Artemis

---

## Transacted Sessions

A session may be specified as transacted. Each transacted session supports a single series of transactions.

**Each transaction groups a set of message sends into an atomic unit of work.**

A transaction is completed using either its session's Commit method or its session's Rollback method. The completion of a session's current transaction automatically begins the next. The result is that a transacted session always has a current transaction within which its work is done.

### Create a transacted session

To create a transacted session, set the parameter of CreateSession to amTransactional as shown in the code example

#### Code example

```
Session := Connection.CreateSession(amTransactional);
```

<sup>11</sup> [https://stomp.github.io/stomp-specification-1.2.html#SUBSCRIBE\\_ack\\_Header](https://stomp.github.io/stomp-specification-1.2.html#SUBSCRIBE_ack_Header)



or (using the older API version)

#### Code example

```
Session := Connection.CreateSession(True, amTransactional);
```

This code will automatically start a new transaction for this session.

## Send messages

Now send messages using the transacted session.

#### Code example

```
Destination := Session.CreateQueue('testqueue');
Producer := Session.CreateProducer(Destination);
Producer.Send(Session.CreateTextMessage('This is a test message'));
```

## Committing a transaction

If your client code has successfully sent its messages, the transaction must be committed to make the messages visible on the destination.

#### Code example

```
// send messages ...

finally
    // commit all messages
    Session.Commit;
end;
```

Note: committing a transaction automatically starts a new transaction

## Rolling back a transaction

If your client code runs wants to undo the sending of its messages, the transaction may be rolled back, and the messages will not become visible on the destination.

## Code example

```
// send messages ...

except
  ...
  // error!
  Session.Rollback;
  ...
end;
```

Note: rolling back a transaction automatically starts a new transaction. A transacted session will be rolled back automatically if the connection is closed.

## Transacted message acknowledgement

Some library versions (see table "Communication Adapters" on page 13) support transactions also for the acknowledgement of received messages.

When a transaction is rolled back or the connection is closed without a commit, messages which have been acknowledged after the transaction start will return to unacknowledged state.

## Code example

```
// receive in a transacted session
Session := Connection.CreateSession(True, amClientAcknowledge);
Queue := Session.CreateQueue(GetQueueName);
Consumer := Session.CreateConsumer(Queue);
Msg := Consumer.Receive(1000);

// process the message
...

// acknowledge the message
Msg.Acknowledge;

...

// in case of errors, roll back all acknowledgements
Session.Rollback;
```

This is an experimental feature. It requires the STOMP 1.2 communication protocol.

# Destinations

---

## Introduction

The API supports two models:<sup>12</sup>

1. point-to-point or queuing model
2. publish and subscribe model

In the point-to-point or queuing model, a producer posts messages to a particular queue and a consumer reads messages from the queue. Here, the producer knows the destination of the message and posts the message directly to the consumer's queue. It is characterized by following:

- Only one consumer will get the message
- The producer does not have to be running at the time the receiver consumes the message, nor does the receiver need to be running at the time the message is sent
- Every message successfully processed is acknowledged by the receiver

The publish/subscribe model supports publishing messages to a particular message topic. Zero or more subscribers may register interest in receiving messages on a particular message topic. In this model, neither the publisher nor the subscriber know about each other. A good metaphor for it is anonymous bulletin board. The following are characteristics of this model:

- Multiple consumers can get the message
- There is a timing dependency between publishers and subscribers. The publisher has to create a subscription in order for clients to be able to subscribe. The subscriber has to remain continuously active to receive messages, unless it has established a durable subscription. In that case, messages published while the subscriber is not connected will be redistributed whenever it reconnects.

---

## Create a new Destination

### Queues

A queue can be created using the `CreateQueue` method of the `Session`.

Code example

<sup>12</sup> Java Message Service. (2007, November 21). In Wikipedia, The Free Encyclopedia. [http://en.wikipedia.org/wiki/Java\\_Message\\_Service](http://en.wikipedia.org/wiki/Java_Message_Service)

```
Destination := Session.CreateQueue('foo');  
Consumer := Session.CreateConsumer(Destination);
```

The queue can then be used to send or receive messages using implementations of the `IMessageProducer` and `IMessageConsumer` interfaces. (See next chapter for an example)

## Topics

A topic can be created using the `CreateTopic` method of the `Session`.

### Code example

```
Destination := Session.CreateTopic('bar');  
Consumer := Session.CreateConsumer(Destination);
```

The topic can then be used to send or receive messages using implementations of the `IMessageProducer` and `IMessageConsumer` interfaces. (See next chapter for an example).

# Producer and Consumer

---

## Message Producer

A client uses a MessageProducer object to send messages to a destination. A MessageProducer object is created by passing a Destination object to a message-producer creation method supplied by a session.

### Code example

```
Destination := Session.CreateQueue('foo');  
Producer := Session.CreateProducer(Destination);  
Producer.Send(Session.CreateTextMessage('Test message'));
```

A client can specify a default delivery mode, priority, and time to live for messages sent by a message producer. It can also specify the delivery mode, priority, and time to live for an individual message.

## Persistent messages

The delivery mode for outgoing messages may be set to persistent in one of two ways. From the docs for TBMessageProducer: "A client can specify a **default delivery mode**, priority, and time to live for messages sent by a message producer. It can also specify the delivery mode, priority, and time to live for an individual message."

## Setting the default delivery mode

### Code example

```
Destination := Session.CreateQueue('foo');  
Producer := Session.CreateProducer(Destination);  
Producer.DeliveryMode := dmPersistent;  
Producer.Send(Session.CreateTextMessage('Test message'));
```

## Setting the delivery mode for an individual message

### Code example

```
Destination := Session.CreateQueue('foo');
```

```

Producer := Session.CreateProducer(Destination);
Producer.Send(Session.CreateTextMessage('Test message'), dmPersistent,
BTBrokerConsts.DEFAULT_PRIORITY, 0);

```

---

## Message Consumer

A client uses a MessageConsumer object to receive messages from a destination. A MessageConsumer object is created by passing a Destination object to a message-consumer creation method supplied by a session.

### Code example

```

Destination := Session.CreateQueue('foo');
Consumer := Session.CreateConsumer(Destination);

```

## Message Selector

A message consumer can be created with a **message selector**<sup>13</sup>.

A message selector allows the client to restrict the messages delivered to the message consumer to those that match the selector.

---

## Synchronous Receive

A MessageConsumer offers a Receive method which can be used to consume exactly one message at a time.

### Code example

```

while I < EXPECTED do
begin
  TextMessage := Consumer.Receive(1000) as ITextMessage;
  if Assigned(TextMessage) then
  begin
    Inc(I);
    TextMessage.Acknowledge;
    L.Info(Format('%d %s', [I, TextMessage.Text]));
  end;
end;

```

<sup>13</sup>The RabbitMQ message broker does not support message selectors

```
end;
```

## Receive and ReceiveNoWait

There are three different methods for synchronous receive:

- Receive**                      The Receive method with no arguments will block (wait until a message is available).
- Receive(Timeout)**        The Receive method with a timeout parameter will wait for the given time in milliseconds. If no message arrived, it will return nil.
- ReceiveNoWait**            The ReceiveNoWait method will return immediately. If no message arrived, it will return nil.

## Durable Subscriptions

---

### Description

If a client needs to receive all the messages published on a topic, including the ones published while the subscriber is inactive, it uses a durable `TopicSubscriber`.

The message broker retains a record of this durable subscription and insures that all messages from the topic's publishers are retained until they are acknowledged by this durable subscriber or they have expired.<sup>14</sup>

The combination of the `clientId` and durable subscriber name uniquely identifies the durable topic subscription.

After you restart your program and re-subscribe, the broker will know which messages you need that were published while you were away.

### Creation

The `Session` interface contains the `CreateDurableSubscriber` method which creates a durable subscriber to the specified topic.

A durable subscriber `MessageConsumer` is created with a unique `clientId` and durable subscriber name.

Only **one** thread can be actively consuming from a given logical topic subscriber.

<sup>14</sup> <http://download.oracle.com/javaee/5/api/javax/jms/TopicSession.html>



# Temporary Queues

---

## Introduction

“Temporary destinations (temporary queues or temporary topics) are proposed as a lightweight alternative in a scalable system architecture that could be used as unique destinations for replies. Such destinations have a scope limited to the connection that created it, and are removed on the server side as soon as the connection is closed.” (“Designing Messaging Applications with Temporary Queues”, by Thakur Thribhuvan <sup>15</sup>)

## Library Support

Temporary destinations are supported by

- ActiveMQ
- OpenMQ
- RabbitMQ

## Resource Management

The session should be closed as soon as processing is completed so that TemporaryQueues will be deleted on the server side.

<sup>15</sup> <http://onjava.com/pub/a/onjava/2007/04/10/designing-messaging-applications-with-temporary-queues.html>

## Message Options

---

### Standard Properties

The Apache ActiveMQ message broker supports some JMS standard properties in the STOMP adapter. These properties are based on the JMS specification of the Message interface.<sup>16</sup>

Habari Client libraries for other message brokers may support a subset of these standard properties.

Note: If your application makes use of these properties, your application depends on a broker-specific feature which is not guaranteed to be available in the STOMP adapter of other message brokers

### Properties for outgoing messages

|                           |   |
|---------------------------|---|
| JMSCorrelationID          | The correlation ID for the message.                                     |
| JMSExpiration             | The message's expiration value.   |
| JMSDeliveryMode           | Whether or not the message is persistent. <sup>17</sup>                 |
| JMSPriority <sup>18</sup> | The message priority level.   |
| JMSReplyTo                | The Destination object to which a reply to this message should be sent. |

### Properties for incoming messages

|                  |  |
|------------------|--|
| JMSCorrelationID | The correlation ID for the message.            |
| JMSExpiration    | The message's expiration value.                |
| JMSDeliveryMode  | Whether or not the message is persistent.      |
| JMSPriority      | The message priority level.                    |
| JMSTimestamp     | The timestamp the broker added to the message. |

<sup>16</sup> <http://download.oracle.com/javaee/5/api/javax/jms/Message.html>

<sup>17</sup> For sending persistent messages please see documentation for `IMessageProducer`

<sup>18</sup> Clients set the `JMSPriority` not directly, but either on the producer or as a parameter in the `Send` method

|              |   |
|--------------|---|
| JMSMessageId | The message ID which is set by the provider.                            |
| JMSReplyTo   | The Destination object to which a reply to this message should be sent. |

---

## Reserved property names

Some headers names are defined by the Stomp specifications, and by broker-specific extensions of the Stomp protocol. These reserved Stomp header names can not be used as names for user defined properties.

Note                                      The client library will raise an Exception if the application tries to send a message with a reserved property name.

## Examples

- login
- passcode
- transaction
- session
- message
- destination
- id
- ack
- selector
- type
- content-length
- content-type
- correlation-id
- expires
- persistent
- priority
- reply-to
- message-id
- timestamp
- transformation
- client-id
- redelivered

## Prefix for custom headers

A common practice to avoid name collisions is using a prefix for your own properties (example: **x-type** instead of **type**).

---

## Selectors

Selectors are a way of attaching a filter to a subscription to perform content based routing. For more documentation on the detail of selectors see the reference on `javax.jms.Message`<sup>19</sup>.

## Supported message brokers

Message selectors are supported by

- Habari Client for ActiveMQ  
Habari Client for Artemis
- Habari Client for OpenMQ

### Code example

```
Consumer := Session.CreateConsumer(Destination, 'type='car' and color='blue');
```

All supported brokers allow supports string type properties and operations in selectors. ActiveMQ also allows integer properties and operations in selectors (see special note<sup>20</sup>).

19 <http://docs.oracle.com/javaee/5/api/javax/jms/Message.html>

20 <http://activemq.apache.org/selectors.html>

# Object Messages

---

## Introduction

### Object Serialization

Object serialization is the process of saving an object's state to a sequence of bytes, as well as the process of rebuilding those bytes into a live object at some future time.<sup>21</sup> In messaging applications, object serialization is required to transfer objects between clients, but also to store objects on the broker if they are declared persistent.

---

## Message Transformers

| Style | Message Type  | Library         | Unit                                |
|-------|---------------|-----------------|-------------------------------------|
| XML   | ObjectMessage | OmniXML         | BTMessageTransformerXMLOmni         |
| XML   | ObjectMessage | NativeXml       | BTMessageTransformerXMLNative       |
| XML   | MapMessage    | OmniXML         | BTMessageTransformerXMLMapOmni      |
| XML   | MapMessage    | NativeXml       | BTMessageTransformerXMLMapNative    |
| XML   | MapMessage    | IDocument       | BTMessageTransformerXMLMapDocument  |
| JSON  | MapMessage    | JsonDataObjects | BTMessageTransformerJSONDataObjects |

Table 4: Message Transformer Implementations

## Memory Management

### Outgoing Objects

The message transformer will not free objects which have been sent. To release the memory, the application has to explicitly free them when they are no longer used.

### Incoming Objects

The message transformer will create an object instance when an object message has been received. To avoid memory leaks, the application must free this instance when it is no longer in use.

<sup>21</sup> <http://www.oracle.com/technetwork/articles/java/javaserial-1536170.html>

## Assign a Message Transformer

To insert an object decoder / encoder in the message processing chain, create a message transformer instance and assign it to the connection's `MessageTransformer` property.

The constructor of message transformers for object exchange takes one argument, which is the **class** of the serialized object. In this example, `SamplePojo` is the class.

### Code example

```
Connection: IConnection;
...

with (Connection as IMessageTransformerSupport) do
begin
    MessageTransformer := TBTMessageTransformerXMLOmni.Create(SamplePojo);
end;

...
Connection.Start;
```

You can also use the helper procedure `SetTransformer` in unit `BTConnection`:

### Code example

```
Connection: IConnection;
...

SetTransformer(Connection, TBTMessageTransformerXMLOmni.Create(SamplePojo));

...
Connection.Start;
```

## Create and Send an ObjectMessage

1. create a `IObjectMessage` instance using `ISession#CreateObjectMessage`
2. send the object message to the broker using `IMessageProducer#Send`

### Code example

```
ObjectMessage := Session.CreateObjectMessage(Instance);
Producer.Send(ObjectMessage);
```

## Complete Example using NativeXml

From ObjectExchangeTests.pas.

Send:

### Code example

```
procedure TObExTestCase.TestXMLNative;
var
  ObjectMessage: IObjectMessage;
  Obj: SamplePojo;
begin
  // send
  Connection := TBTPConnection.MakeConnection;
  try
    SetTransformer(Connection, TBTPMessageTransformerXMLNative.Create(SamplePojo));
    Connection.Start;
    Session := Connection.CreateSession(False, amAutoAcknowledge);
    Destination := Session.CreateQueue('TOOL.OBJECT.XML');
    Producer := Session.CreateProducer(Destination);
    Obj := SamplePojo.Create;
    try
      Obj.messageText := 'test';
      Obj.messageNo := 0;
      ObjectMessage := Session.CreateObjectMessage(Obj);
      ObjectMessage.SetStringProperty(SH_TRANSFORMATION + '-custom',
        TRANSFORMER_ID_OBJECT_XML); // required for "Delphi Only" object exchange
      Producer.Send(ObjectMessage);
    finally
      Obj.Free;
    end;
  finally
    Connection.Close;
  end;
end;
```

Receive:

### Code example

```
Connection := TBTPConnection.MakeConnection;
try
  SetTransformer(Connection, TBTPMessageTransformerXMLNative.Create(SamplePojo));
  Connection.Start;
  Session := Connection.CreateSession(False, amClientAcknowledge);
  Destination := Session.CreateQueue('TOOL.OBJECT.XML');
  Consumer := Session.CreateConsumer(Destination);
```

## 48 *Habari Client for Artemis 6.7*

```
ObjectMessage := Consumer.Receive(1000) as IObjectMessage;
if Assigned(ObjectMessage) then
begin
    ObjectMessage.Acknowledge;
    Obj := ObjectMessage.GetObject as SamplePojo;
    try
        CheckEquals('test', Obj.messageText);
        CheckEquals(0, Obj.messageNo);
    finally
        Obj.Free;
    end;
end;
finally
    Connection.Close;
end;
end;
```



## Stomp 1.2

---

### Connection configuration

A connection string can use additional URL parameters to configure Stomp version 1.1 and 1.2

All Parameters are case sensitive.

Parameters can be omitted to use the default value.

| Switch                               | Description   | Default                    |
|--------------------------------------|---|----------------------------|
| connect.accept-version <sup>22</sup> | Supported Stomp versions in ascending order   | Broker specific, see below |
| connect.host <sup>23</sup>           | <b>The name of a virtual host that the client wishes to connect to.</b> It is recommended clients set this to the host name that the socket was established against, or to any name of their choosing. If this header does not match a known virtual host, servers supporting virtual hosting MAY select a default virtual host or reject the connection. | Server URI                 |
| connect.heart-beat <sup>24</sup>     | Heart beat (outgoing, incoming)   | 0,0                        |

#### Default Stomp version (broker-specific)<sup>25</sup>

If the connection URL does not contain the connect.accept-version parameter, the client library will add an accept-version header to the CONNECT frame with the value defined in the SH\_DEFAULT\_STOMP\_VERSION constant in the BTBrokerConsts unit.

| Default Stomp version |         |        |          |
|-----------------------|---------|--------|----------|
| ActiveMQ              | Artemis | OpenMQ | RabbitMQ |
| 1.2                   | 1.2     | 1.0    | 1.2      |

<sup>22</sup> [http://stomp.github.com/stomp-specification-1.2.html#protocol\\_negotiation](http://stomp.github.com/stomp-specification-1.2.html#protocol_negotiation)

<sup>23</sup> [http://stomp.github.com/stomp-specification-1.2.html#CONNECT\\_or\\_STOMP\\_Frame](http://stomp.github.com/stomp-specification-1.2.html#CONNECT_or_STOMP_Frame)

<sup>24</sup> <http://stomp.github.com/stomp-specification-1.2.html#Heart-beating>

<sup>25</sup> Since version 5.1 (2017.06)

### Connection Factory Code Example:

#### Code example

```
Factory := TBTConnectionFactory.Create(  
    'stomp://localhost:61613?connect.accept-version=1.2&connect.heart-beat=1000,0');
```

This example creates a connection factory with these connection settings

host: localhost

port: 61613

accept-version: 1.2

heart-beat: 1000,0

- virtual host is localhost
- the client requests Stomp 1.2 protocol
- client heart beat interval is 1000 milliseconds, no server heart beat signals

## Specification

For details see the Stomp specification pages:

<http://stomp.github.com//stomp-specification-1.1.html>

<http://stomp.github.com//stomp-specification-1.2.html>

---

## Sending heart-beat signals

A client can use the **SendHeartbeat** method of the connection object to send a heart-beat byte (newline 0x0A).

SendHeartbeat is a method of the IHeartbeat interface, which is declared in the BTSessionIntf unit. A cast of the IConnection object is required to access this method.

#### Code example

```
(Connection as IHeartbeat).SendHeartbeat;
```

Notes:

- the client application code is responsible for sending a heartbeat message within the maximum interval which was specified in the connect parameter – the Habari Client library does not send heart-beats automatically
- client messages which are sent after the heart-beat interval expires may be lost

---

## Checking for incoming heartbeats

The Habari client library stores a time-stamp of the last incoming data. If the time which elapsed since this time-stamp is greater than two times the heart-beat interval, calling **CheckHeartbeat** will raise an exception of type `EBTStompServerHeartbeatMissing`.

Code example

```
(Connection as IHeartbeat).CheckHeartbeat;
```

Notes:

- the method raises an exception if the connection does not use server-side heart-beating
- the method only checks the time elapsed since the last heart-beat, it does not try to read any data from the connection

---

## Reading server-side heartbeats

If the client never needs to consume any messages, but still needs to check for server-side heartbeats, it can use the **ReceiveHeartbeat** method of the connection object.

This method takes one argument, `TimeOut`.

The function returns `True` if it found at least one heart-beat signal on the connection.

Calling `ReceiveHeartbeat` is only useful for applications which never call `Receive`, to check if the server is still healthy, and to consume the pending heart-beat signals from the connection.

If the client reads messages (using `Consumer.Receive`), calling `ReceiveHeartbeat` is not required.

## Example Applications

| Directory               | Description  |
|-------------------------|--|
| common                  | Shared units (see below)   |
| common-consumertool     | Receive messages from broker   |
| common-consumertool-fpc | Free Pascal version of ConsumerTool  |
| common-producertool     | Send messages to broker  |
| common-producertool-fpc | Free Pascal version of producertool  |
| common-producertool-ssl | Send messages to broker with SSL connection  |
| common-tests            | DUnit tests  |
| common-tests-fpc        | FPCUnit tests  |
| delphichat              | Simple chat client (Delphi 2009)   |
| heartbeat-server        | Uses server-side heart-beating to check the connection / server health <sup>26</sup>   |
| performance             | Multi-threaded performance test application (Delphi 2009)  |
| reconnect               | Send messages and reconnect on connection failure  |
| rpc                     | Use temporary queues to implement request/response style communication (not supported on all message brokers <sup>27</sup> ) |
| textmessage             | Simple text message example  |
| throughput              | Produces and consumes messages continuously  |
| throughput-fpc          | Free Pascal version of throughput  |
| transactions            | Transaction example  |
| tutorial1               | Tutorial one   |
| tutorial2               | Tutorial two   |

Table 5: Example Applications (in alphabetic order)


<sup>26</sup> Requires STOMP 1.2; not supported by OpenMQ

<sup>27</sup> Not available with ActiveMQ Artemis and HornetQ message broker

## Shared units for demo projects

The directory `demo/common` contains shared units:

- connection configuration form
- command line parameter support class
- LoggingHelper example unit (see “Logging with SLF4P” on page 64)



*Illustration 2: Connection configuration dialog example*


---

## ConsumerTool

The ConsumerTool demo may be used to receive messages from a queue or topic. This example application is configurable by command line parameters, all are optional.

| Parameter                  | Default Value      | Description  |
|----------------------------|--------------------|--|
| <b>AckMode</b>             | CLIENT_ACKNOWLEDGE | Acknowledgment mode, possible values are: CLIENT_ACKNOWLEDGE, AUTO_ACKNOWLEDGE or SESSION_TRANSACTED |
| <b>ClientId</b>            |                    | Client Id for durable subscriber   |
| <b>ConsumerName</b>        | Habari             | name of the message consumer - for durable subscriber  |
| <b>Durable</b>             | false              | true: use a durable subscriber   |
| <b>MaximumMessages</b>     | 10                 | expected number of messages  |
| <b>Password</b>            |                    | Password   |
| <b>PauseBeforeShutDown</b> | false              | true: wait for key press   |
| <b>ReceiveTimeOut</b>      | 0                  | consume messages while they continue to be delivered within the given time out                       |
| <b>SleepTime</b>           | 0                  | time to sleep after receive  |
| <b>Subject</b>             | TOOL.DEFAULT       | queue or topic name  |
| <b>Topic</b>               | false              | true: topic false: queue   |
| <b>Transacted</b>          | false              | true: transacted session   |
| <b>URL</b>                 | localhost          | server url   |
| <b>User</b>                |                    | user name  |
| <b>Verbose</b>             | true               | verbose output   |

*Table 6: ConsumerTool Command Line Options*



```

C:\Users\mj\Desktop\Sandbox\Habari Client libraries\Habari RabbitMQ\demo\c...
Habari Client for RabbitMQ 1.9 (c) 2011-2013 Michael Justin
Connecting to URL: stomp://localhost:61613
Consuming queue: ExampleQueue
Using a non-durable subscription
We are about to wait until we consume: 10 message(s) then we will shutdown
Received: Message: 7 sent at: 08.01.2014 10:35:39      ...
Received: Message: 8 sent at: 08.01.2014 10:35:39      ...
Received: Message: 9 sent at: 08.01.2014 10:35:39      ...
Received: Message: 0 sent at: 08.01.2014 17:11:20      ...
Received: Message: 1 sent at: 08.01.2014 17:11:21      ...
Received: Message: 2 sent at: 08.01.2014 17:11:21      ...
Received: Message: 3 sent at: 08.01.2014 17:11:21      ...
Received: Message: 4 sent at: 08.01.2014 17:11:21      ...
Received: Message: 5 sent at: 08.01.2014 17:11:21      ...
Received: Message: 6 sent at: 08.01.2014 17:11:21      ...
Closing connection

```

Illustration 3: ConsumerTool demo application

## Examples

Receive 1000 messages from local broker

```
ConsumerTool --MaximumMessages=1000
```

Receive 10 messages from local broker and wait for any key

```
ConsumerTool --PauseBeforeShutDown
```

Use a transacted session to receive 10,000 messages from local broker

```
ConsumerTool --MaximumMessages=10000 --Transacted --AckMode=SESSION_TRANSACTED
```

## ProducerTool

The ProducerTool demo can be used to send messages to the broker. It is configurable by command line parameters, all are optional.

| Parameter           | Default      | Description                            |
|---------------------|--------------|--|
| <b>MessageCount</b> | 10           | Number of messages                     |
| <b>MessageSize</b>  | 255          | Length of a message in bytes           |
| <b>Persistent</b>   | false        | Delivery mode 'persistent'             |
| <b>SleepTime</b>    | 0            | Pause between messages in milliseconds |
| <b>Subject</b>      | TOOL.DEFAULT | Destination name                       |
| <b>TimeToLive</b>   | 0            | Message expiration time                |
| <b>Topic</b>        | false        | Destination is a topic                 |
| <b>Transacted</b>   | false        | Use a transaction                      |
| <b>URL</b>          | localhost    | Message broker URL                     |
| <b>Verbose</b>      | true         | Verbose output                         |
| <b>User</b>         |              | User name                              |
| <b>Password</b>     |              | Password                               |

Table 7: ProducerTool Command Line Options

```

C:\Users\mj\Desktop\Sandbox\Habari Client libraries\Habari RabbitMQ\demo\c...
Habari Client for RabbitMQ 1.9 (c) 2011-2013 Michael Justin
Connecting to URL: stomp://localhost:61613
Publishing a Message with size 255 to queue: ExampleQueue
Using non-persistent messages
Sleeping between publish 0 ms
Sending message: Message: 0 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 1 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 2 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 3 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 4 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 5 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 6 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 7 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 8 sent at: 10.01.2014 10:49:30 ...
Sending message: Message: 9 sent at: 10.01.2014 10:49:30 ...
Done.

```

Illustration 4: ProducerTool demo application

## Examples

Send 10,000 messages to the queue `TOOL.DEFAULT` on the local broker



```
ProducerTool --MessageCount 10000
```

Send 10 messages to the topic ExampleTopic on the local broker

```
ProducerTool --Topic --Subject=ExampleTopic
```

---

## Performance test

The performance test application provides a GUI for multi-threaded sending and receiving of messages.

- A broker configuration dialog can be invoked by clicking the URL field
- The communication library (Indy or Synapse) can be selected
- Number and length of messages and thread number can be adjusted using the sliders

For every thread a message queue with the name ExampleQueue.<n> will be used.




Illustration 5: Performance Test Application

Habari Client for Artemis 5.1 includes an enhanced performance test application, which optionally collects message rates of multiple test runs and displays the sample median. Shown above is an example for a client configuration:

- 21 test runs (triggered by a shift-click on the test button)
- 2000 messages per thread
- 210 bytes payload
- two producer threads, two consumer threads

To start the long-running tests, shift-click on the run button. Taking all test samples takes around ten seconds.

## Throughput test

This example application is configurable by command line parameters, all are optional.

| Parameter       | Default Value     | Description    |
|-----------------|-------------------|----------------|
| <b>Password</b> | (broker-specific) | Password       |
| <b>Subject</b>  | ExampleTopic      | Topic name     |
| <b>URL</b>      | (broker-specific) | Connection URL |
| <b>User</b>     | (broker-specific) | User name      |

Table 8: Throughput Test Tool Command Line Options

## Examples

Use remote broker 'mybroker' and specify user and password

```
tptest --url=stomp://mybroker --user=test1 --password=secret
```

```

C:\Users\mj\Desktop\Sandbox\Habari Client libraries\Habari Apollo\target\dem...
Habari Client for Apollo 1.6 (c) 2008-2013 Michael Justin
Connecting to URL: stomp://localhost:61613
Consuming: ExampleTopic
Press Ctrl+C to stop
00:02 tx/rx 29213/12152 14562/6057 msgs/sec ( 68/165 microsecs/msg)
00:04 tx/rx 40136/23454 9981/5832 msgs/sec (100/171 microsecs/msg)
00:06 tx/rx 49693/33786 8231/5596 msgs/sec (121/178 microsecs/msg)
00:08 tx/rx 59257/42738 7358/5307 msgs/sec (135/188 microsecs/msg)
00:10 tx/rx 70173/54674 6980/5438 msgs/sec (143/183 microsecs/msg)
00:12 tx/rx 81096/65864 6719/5457 msgs/sec (148/183 microsecs/msg)
00:14 tx/rx 94749/76807 6706/5436 msgs/sec (149/183 microsecs/msg)
00:16 tx/rx 102941/87498 6381/5424 msgs/sec (156/184 microsecs/msg)

```

Illustration 6: Throughput test tool output

# Unit Tests

---

## Introduction

Habari Client libraries include DUnit and FPCUnit tests. They require the classic DUnit framework (included in Delphi 2009) or FPCUnit (included in Lazarus 2.6).

The test projects are installed in the common-tests and common-tests-fpc folders.

---

## Test project configuration

### Logging

To switch on SLF4P logging, add the conditional symbol `HABARI_LOGGING` (see chapter 'Logging with SLF4P') and rebuild the project. Set the `DEFAULT_LOG_LEVEL` constant in unit `TestHelper` to a valid SLF4P level.

### Raw message logging

To switch on raw logging, add the conditional symbol `HABARI_RAW_TRACE` and rebuild the project. The project has the `{$APPTYPE CONSOLE}` flag, which will cause a console window to open.

### Optional units

To switch on tests for optional units (object message exchange), add the conditional symbol `TEST_OPTIONAL_UNITS` and rebuild the project.

### Synapse communication adapter

To switch from Indy to Synapse for the tests, add the conditional symbol `HABARI_TEST_SYNAPSE` and rebuild the project.

---

## Test units

The common-tests folder contains these units

| <b>Test setup and test case base classes</b> |  |
|--|--|
| TestHelper                                   | Main test set-up and utility unit, contains no tests |
| HabariTestCase                               | Test case base classes used for most tests           |

| <b>Unit tests</b>                 |   |
|-----------------------------------|---|
| ApiTests                          | Tests Habari Client core API methods – part 1                       |
| BasicTests                        | Tests Habari Client core API methods – part 2                       |
| BrokerExtensionsTests             | Tests broker-specific features and extensions of the STOMP protocol |
| HabariExtensionsTests             | Tests non-standard features provided by the Habari Client library   |
| HabariTypesTests                  | Tests internal data types   |
| ObjectExchangeTests <sup>28</sup> | Tests object message exchange (for Delphi DUnit only)               |
| Stomp12Tests                      | Tests features introduced with version 1.2 of the STOMP standard    |
| StubServerTests                   | Tests using a simple local Stomp server                             |

Free Pascal specific test units are in the folder common-tests-fpc

---

## Test execution

### Requirements

The test projects require a message broker running on the local system, which accepts STOMP connections on the default port, with the default user credentials. User name and password for the default user are defined in unit BTBrokerConsts.

### Test destinations

Most tests create a test-specific destination (queue or a topic) to reduce the risk of side effects.

The name of the destination is the combination of the test class name and the unit test name.

Note: the unit tests will not clean up or remove these destination objects after usage.

<sup>28</sup>only added to the test suite if TEST\_OPTIONAL\_UNITS is defined

## **STOMP 1.2**

Since Habari Client for Artemis 5.0, the unit test use STOMP 1.2 for connections.

## Logging with SLF4P

---

### Introduction

Habari Client libraries include the free open source logging framework SL4FP as an optional dependency.

SLF4P is available at <https://github.com/michaelJustin/slf4p>

---

### IDE and project configuration

In order to compile with SLF4P support,

1. include the path to the slf4p library in the project search or in the global library path
2. add the conditional symbol HABARI\_LOGGING to the project options

### Delphi

- choose Project | Options... | Delphi Compiler > Conditional defines
- add HABARI\_LOGGING

### Lazarus

- choose Project | Project Options ... | Compiler Options > Other
- add -dHABARI\_LOGGING in the Custom options field

---

### LoggingHelper unit

A simple LoggingHelper unit is located in the demo\common\ directory and can be copied to a project to add slf4p support with little extra coding.

#### Code example

```
uses
  LoggingHelper,
  ...
```



```
begin
  // set up logging
  LoggingHelper.ConfigureLogging;
```

The LoggingHelper unit may be adjusted to your configuration needs. Here is an example which uses the SimpleLogger implementation (included in SLF4P).

#### Code example

```
unit LoggingHelper;

interface

uses
  {$IFDEF HABARI_LOGGING}
  djLogOverSimpleLogger, SimpleLogger
  {$ENDIF HABARI_LOGGING};

const
  DEFAULT_LOG_LEVEL = 'info';

procedure ConfigureLogging(const LogLevel: string = DEFAULT_LOG_LEVEL);

implementation

procedure ConfigureLogging(const LogLevel: string);
begin
  {$IFDEF HABARI_LOGGING}
  SimpleLogger.Configure('defaultLogLevel', LogLevel);
  SimpleLogger.Configure('showDateTime', 'true');
  {$ENDIF HABARI_LOGGING}
end;

end.
```

## Conditional Symbols

---

### Caution

**All conditional symbols enable experimental or optional features, which are not covered by the free basic support plan.** Feedback (suggestions for improvements, feature requests, and bug reports) are always welcome.

---

### Conditional symbols for release builds

#### **HABARI\_ALLOW\_UNKNOWN\_URL\_PARAMS**

**Disables strict connection URL parameter checking.**

If this symbol is defined, connection URLs may contain arbitrary parameters. By default, the library only accepts well-known connection parameters and raises an exception for unknown parameters.

**Broker versions:** all broker versions.

#### **HABARI\_LOGGING**

**Enables logging support.** Requires the open source SLF4P logging facade.

**Broker versions:** all broker versions.

See also: Logging with SLF4P

#### **HABARI\_SSL\_SUPPORT**

**Enables SSL support.** Support for SSL connections is an advanced / optional feature, technical support is not included in the basic support plan.

The directory source/optional contains example implementations of Indy and Synapse adapter classes with OpenSSL support. Please note that these are basic implementations and not supported in the free basic support plan.

**Broker versions:** all broker versions.

See also: SSL/TLS Support

## HABARI\_TCP\_KEEPALIVE

**Enables configuration option for TCP keep-alive.**

For details please see chapter **Connection URL parameters**.

**Broker versions:** all broker versions.

Indy communication adapter only

## HABARI\_USE\_INTERCEPT

**Enables detailed logging of Stomp message frames**

This uses the Indy interceptor implementation in unit IdInterceptSimLog.

All communication data will be logged to a file. A new file will be created for every new STOMP connection. The file is located in a folder below the current working directory.

If this symbol is defined in a release build, a compiler warning will be emitted:

```
HABARI_USE_INTERCEPT should not be used for release builds
```

**Broker versions:** all broker versions.

Indy communication adapter only

Note: this feature requires permissions

- create a directory in the current directory if it does not exist
- create files

---

## Conditional symbols for unit test projects

### HABARI\_TEST\_OPTIONAL\_UNITS

Enables tests for experimental / optional units.

### HABARI\_TEST\_SYNAPSE

Enables Synapse communication adapter in DUnit/FPCUnit tests, default is Indy.

**Supported for:** all versions.

### HABARI\_TEST\_USE\_MGMT\_API

**Enables additional test steps**

## 68 *Habari Client for Artemis 6.7*

If this symbol is defined, a broker-specific management client will be used to perform one or more of these actions:

- create destinations on the message broker (test preparation)
- destroy destinations on the message broker (cleanup)
- check destinations for their pending message count

Actual actions depend on the message broker type, see `HabariTestCase` unit source code for details.

Only available with the DUnit test suite, not for FPCUnit.

Available since version 5.2.0 (2017.10)

Status: This is work in progress / experimental

**Broker versions:** Apache ActiveMQ, Apache ActiveMQ Artemis and RabbitMQ. For OpenMQ, a “no op” client will be used to keep the test source code compatible between all broker versions.

## SSL/TLS Support

---

### SSL communication adapter classes

Habari Client for Artemis includes two **experimental** adapter classes for usage with OpenSSL, one for Indy (Internet Direct) and one for Synapse. The units for these classes are in the source\optional folder.

| Adapter Class           | Unit                    |
|-------------------------|-------------------------|
| TBCommAdapterIndySSL    | BTCommAdapterIndySSL    |
| TBCommAdapterSynapseSSL | BTCommAdapterSynapseSSL |

Table 9: Communication Adapters with SSL Support

### Mixed Use

It is possible to use SSL and non-SSL connections in the same project:

- connections with the "stomp://" scheme will remain unencrypted
- connections with the "stomp+ssl://" scheme will use SSL

### SSL configuration

The TBCommAdapterIndySSL class includes very basic configuration of the Indy SSL handler. Your server or your specific security requirements may require additional configuration.

---

### Indy SSL Demo

A demo application is included in **common-producertool-ssl**.

#### Code example

```
program ProducerToolIndySSL;

{$APPTYPE CONSOLE}

uses
```

```

// the Habari Client adapter class for Indy + SSL
BTCommAdapterIndySSL,
// required to set the default adapter
BTAdapterRegistry,
// the common demo unit for the producer tool
ProducerToolUnit in '..\common-producertool\ProducerToolUnit.pas',
// configuration support unit
CommandLineSupport in '..\common\CommandLineSupport.pas',
SysUtils;

begin
  BTAdapterRegistry.SetDefaultAdapter(TBTCommAdapterIndySSL);

  with TProducerTool.Create do
  try
    try
      Run;
    except
      on E:Exception do WriteLn(E.Message);
    end
  finally
    Free;
  end;
  ReadLn;
end.

```

## Notes

- the `TBTCommAdapterIndySSL` class must be registered using `(BTAdapterRegistry.SetDefaultAdapter(TBTCommAdapterIndySSL))`
- the project must be compiled with `HABARI_SSL_SUPPORT`
- the connection URL must be in the form "**stomp+ssl://server.com:sslport**"
- the OpenSSL libraries must be in the application search path

## Example output

```

Habari Client for RabbitMQ 5.1.0 (c) 2008-2017 Michael Justin
Connecting to URL: stomp+ssl://localhost:61614
Publishing a Message with size 255 to queue: ExampleQueue
Using persistent messages
Sleeping between publish 0 ms
313 INFO habari.TBTCommAdapterIndySSL - Verifying SSL certificate
313 INFO habari.TBTCommAdapterIndySSL - Issuer: /C=GB/ST=Greater Manchester/L=Sa
lford/O=COMODO CA Limited/CN=COMODO RSA Domain Validation Secure Server CA
313 INFO habari.TBTCommAdapterIndySSL - Not After: 09.04.2018 01:59:59
313 INFO habari.TBTCommAdapterIndySSL - Verifying SSL certificate
313 INFO habari.TBTCommAdapterIndySSL - Issuer: /C=GB/ST=Greater Manchester/L=Sa

```

```
lford/O=COMODO CA Limited/CN=COMODO RSA Domain Validation Secure Server CA
313 INFO habari.TBTCommAdapterIndySSL - Not After: 09.04.2018 01:59:59
329 INFO habari.TBTStompClient - Connected with RabbitMQ/3.6.10 using STOMP 1.2
Sending message: Message: 0 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 1 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 2 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 3 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 4 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 5 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 6 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 7 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 8 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 9 sent at: 28.06.2017 10:26:43      ...
Done.
```

---

## Support

Support for SSL/TLS connections and the example adapter classes is not included in the basic support package of Habari Client for Artemis.

## Useful Units

---

### BTStreamHelper unit

This unit contains the procedure `LoadBytesFromStream` which can be used to read a file into a `BytesMessage`.

#### Code example

```
// create the message
Msg := Session.CreateBytesMessage;

// open a file
FS := TFileStream.Create('filename.dat', fmOpenRead);

try
  // read the file bytes into the message
  LoadBytesFromStream(Msg, FS);

  Size := Length(Msg.Content);

  // display message content size
  WriteLn(IntToStr(Size) + ' Bytes');

finally
  // release the file stream
  FS.Free;
end;
```

---

### BTJavaPlatform unit

This unit contains some helper functions for Java dates. Java dates are `Int64` values based on the Unix date.

```
function JavaDateToTimeStamp(const JavaDate: Int64): TDateTime;
```

```
function TimeStampToJavaDate(const TimeStamp: TDateTime): Int64;
```



## Library Limitations

---

### MessageConsumer

#### How do I implement synchronous receive from multiple destinations?

The library does not support synchronous receive from more than one destination over a single connection.

To receive messages synchronously (using `Receive` and `ReceiveNoWait`) from two or more destinations, create one connection per destination.

Background: all pending messages in a connection are serialized in one TCP stream, so reading only the messages which come from one of the destinations would require 'skipping' all messages for other destinations.

---

### Message properties

#### Only string data type supported by Stomp

The STOMP protocol uses string type key/value lists for the representation of message properties. Regardless of the method used to set message properties, all message properties will be interpreted as Java Strings by the Message Broker.

As a side effect, the expressions in a Selector are limited to operations which are valid for strings.

Timestamp properties are converted to a Unix time stamp value, which is the internal representation in Java. But still, these values can not be used with date type expressions.

#### Broker-specific exceptions

Apache ActiveMQ 5.6 introduced support for numeric expressions in JMS selectors<sup>8</sup>.

---

### Multi threading

A session supports transactions and it is difficult to implement transactions that are multi-threaded; a session should not be used concurrently by multiple threads.

## **Free Pascal specific restrictions**

- the library has only been tested on the Windows platform
- the included unit test project uses FPCUnit for Free Pascal / Lazarus instead of DUnit
- the third-party libraries for XML and JSON based object exchange do not support Free Pascal
- the library source code use the Delphi mode switch {\$MODE DELPHI}
- other limitations or restrictions may apply

---

## **Broker-specific limitations**

### **Transacted Sessions**

#### **Transactional acknowledging**

The STOMP implementations of Artemis and OpenMQ message broker do not support transactional acknowledging of incoming messages.

#### **Other broker specific limitations**

For broker-specific notes, please read chapter Broker-specific notes.

## Frequently Asked Questions

---

### Technical questions

#### Why am I getting 'undeclared identifier IndyTextEncoding\_UTF8'?

##### Short answer

Your Indy version is too old.

##### Long answer

The library requires a current Indy 10.6.2 version.

##### Solution

Please download a newer Indy version.

#### Why am I getting 'Undeclared identifier: 'TimeSeparator''?

##### Short answer

Your Synapse version does not support your version of Delphi

##### Long answer

Delphi XE4 removed twenty deprecated global variables. For more details, see [http://docwiki.embarcadero.com/RADStudio/XE4/en/Global\\_Variables](http://docwiki.embarcadero.com/RADStudio/XE4/en/Global_Variables).

##### Solution

Please use Indy instead of Synapse or use a compatible version of Synapse.

#### Why am I getting 'Found no matching consumer' errors?

##### Short answer

The client closed a consumer while there still were pending messages on the wire for it, and then tried to receive the pending messages with a new consumer.

##### Long answer

If the client subscribes to a destination, it creates a unique subscription identifier and passes it to the broker. Messages which the broker sends to the client always include this

subscription identifier in their header properties. The client verifies that the subscription id in the incoming message has the same id as the consumer.

If the client closes the consumer before all messages waiting on the wire have been consumed, and creates a new subscription (which has a new unique id), the remaining messages which are waiting on the wire, will have a subscription id which does not match the id of the new subscription. The client will raise an exception if no matching consumer can be found.

## Solution

Do not create another consumer on the same connection while there are still pending messages for the first consumer. To discard all pending messages which are still waiting on the wire, the client can simply close the connection and create a new consumer on a new connection.

## Example

Here is a small code example which causes this error<sup>29</sup>:

### Code example

```
procedure TErrorHandlingTests.TestReceiveMessageForOtherSubscription;
var
  Factory: IConnectionFactory;
  Conn: IConnection;
  Session: ISession;
  Destination: IDestination;
  Producer: IMessageProducer;
  Consumer: IMessageConsumer;
  Msg: IMessage;
begin
  Factory := TBTConnectionFactory.Create;
  Conn := Factory.CreateConnection;
  Conn.Start;
  Session := Conn.CreateSession(amAutoAcknowledge);
  Destination := Session.CreateQueue(GetQueueName);
  Consumer := Session.CreateConsumer(Destination);
  Producer := Session.CreateProducer(Destination);
  Msg := Session.CreateMessage;
  Producer.Send(Msg);
  Consumer.Close;
  Consumer := Session.CreateConsumer(Destination);
  Consumer.Receive(1000);
end;
```

In line 20 and 21, the consumer is closed and a new consumer created for the same destination.

The Receive in line 22 will detect that the incoming message does not have a matching consumer id and raise an `EIllegalStateException`.

<sup>29</sup>This code example is included in the library unit test project

## Online Resources

---

### Third-party libraries

#### Indy

Indy is an open source client/server communications library that supports TCP/UDP/RAW sockets, as well as over 100 higher level protocols including SMTP, POP3, IMAP, NNTP, HTTP, FTP, and many more. Indy is written in Delphi but is available for C++Builder, Delphi, FreePascal, .NET, and Kylix.

Project home <https://www.indyproject.org/>

GitHub <https://github.com/IndySockets>

#### SLF4P

SLF4P is a simple logging facade for Object Pascal, developed with Delphi 2009 and Lazarus 2.0. Tested with DUnit and FPCUnit.

Project home <https://github.com/michaelJustin/slf4p>

#### JsonDataObjects

JsonDataObjects is a JSON parser for Delphi 2009 and newer

GitHub <https://github.com/ahausladen/JsonDataObjects>

#### Synapse

Project home <http://synapse.ararat.cz>

Subversion <http://svn.code.sf.net/p/synalist/code/trunk/>

## Specifications

### Stomp – Simple (or Streaming) Text Oriented Messaging Protocol<sup>30</sup>

|            |   |
|------------|---|
| Stomp home | <a href="https://stomp.github.io/index.html">https://stomp.github.io/index.html</a>                                     |
| Stomp 1.2  | <a href="https://stomp.github.io/stomp-specification-1.2.html">https://stomp.github.io/stomp-specification-1.2.html</a> |
| Stomp 1.1  | <a href="https://stomp.github.io/stomp-specification-1.1.html">https://stomp.github.io/stomp-specification-1.1.html</a> |
| Stomp 1.0  | <a href="https://stomp.github.io/stomp-specification-1.0.html">https://stomp.github.io/stomp-specification-1.0.html</a> |

### Broker-specific Stomp documentation

|          |   |
|----------|---|
| ActiveMQ | <a href="https://activemq.apache.org/stomp.html">https://activemq.apache.org/stomp.html</a>   |
| Artemis  | <a href="https://activemq.apache.org/components/artemis/documentation/latest/stomp.html">https://activemq.apache.org/components/artemis/documentation/latest/stomp.html</a> |
| RabbitMQ | <a href="https://www.rabbitmq.com/stomp.html">https://www.rabbitmq.com/stomp.html</a>   |

---

## Online articles

| Title  | Broker   |
|--|----------|
| Firebird Database Events and Message-oriented Middleware <sup>31</sup> | All      |
| Discover ActiveMQ brokers with Delphi XE4 and Indy 10.6 <sup>32</sup>  | ActiveMQ |
| Official RabbitMQ Management REST API Documentation <sup>33</sup>      | RabbitMQ |
| How to use the RabbitMQ Web-Stomp Plugin <sup>34</sup>                 | RabbitMQ |
| RPC with Delphi client and Java server using RabbitMQ <sup>35</sup>    | RabbitMQ |

<sup>30</sup> [http://en.wikipedia.org/wiki/Streaming\\_Text\\_Oriented\\_Messaging\\_Protocol](http://en.wikipedia.org/wiki/Streaming_Text_Oriented_Messaging_Protocol)

<sup>31</sup> <https://mikejustin.wordpress.com/2012/11/06/firebird-database-events-and-message-oriented-middleware/>

<sup>32</sup> <https://mikejustin.wordpress.com/2013/07/07/discover-activemq-brokers-with-delphi-xe4-and-indy-10-6/>

<sup>33</sup> <https://mikejustin.wordpress.com/2012/10/26/official-rabbitmq-management-rest-api-documentation/>

<sup>34</sup> <https://mikejustin.wordpress.com/2013/11/27/how-to-use-the-rabbitmq-web-stomp-plugin-with-delphi-and-free-pascal/>

<sup>35</sup> <https://mikejustin.wordpress.com/2013/05/21/rpc-with-delphi-client-and-java-server-using-rabbitmq/>

## Online Videos

| Title  | Broker   |
|--|----------|
| Introduction to Messaging With Apache ActiveMQ <sup>36</sup>       | ActiveMQ |
| GlassFish Message Queue – High Availability Clusters <sup>37</sup> | OpenMQ   |

<sup>36</sup> <http://vimeo.com/12654513>

<sup>37</sup> <http://www.youtube.com/watch?v=RHUJBSy3udU>

## Support

---

### **Bug reports and support inquiries**

Please send bug reports and support inquiries to [cases@habarisoft.com](mailto:cases@habarisoft.com), and specify your message broker type and version.

To allow fast processing of your inquiry, please provide a detailed problem description, including configuration and environment, or code examples which help to reproduce the problem.

### **Advanced support**

Advanced and experimental features such as (for example) SSL, third party libraries, Free Pascal, Linux, non-Unicode Delphi versions and message broker configuration are not covered by the basic support scheme.



## Broker-specific notes

---

### Broker configuration

The broker configuration in `etc/broker.xml` needs to be configured according to the example in the Artemis documentation.

```
<address-settings>
  ...
  <address-setting match="queue/#">
    <default-address-routing-type>ANYCAST</default-address-routing-type>
    <default-queue-routing-type>ANYCAST</default-queue-routing-type>
    <auto-delete-addresses>false</auto-delete-addresses>
  </address-setting>
  <address-setting match="topic/#">
    <default-address-routing-type>MULTICAST</default-address-routing-type>
    <default-queue-routing-type>MULTICAST</default-queue-routing-type>
  </address-setting>
  ...
</address-settings>

<wildcard-addresses>
  <delimiter></delimiter>
</wildcard-addresses>
```

### Reference

For further reference see paragraph “Configuring Routing Semantics from the Broker side” in the ActiveMQ Artemis documentation:

- <https://activemq.apache.org/components/artemis/documentation/latest/stomp.html>

## Quick start guide for Apache ActiveMQ Artemis

---

### Installation

For installation, please read the Apache ActiveMQ Artemis instructions:

- <https://activemq.apache.org/components/artemis/documentation/latest/using-server.html>

#### **Windows service**

On Windows you will have the option to run ActiveMQ Artemis as a service.

#### **Start up screen**

At start up, the broker logs information about enabled protocols and ports.

#### **STOMP ports**

STOMP is enabled on ports 5445, 61613 and 61616.

#### **Broker IP address**

The broker is reachable on all network adapters (address 0.0.0.0).

#### **Other protocols**

Other protocols such as AMQP and the OpenWire and HornetQ JMS wire protocols are also enabled by default.

#### **Supported protocol**

Habari Client for Artemis supports the STOMP communication protocol only.

# Index

## Reference

|  |          |                            |          |
|--|----------|----------------------------|----------|
| BTBrokerConsts.....                        | 62       | ISession.....              | 46       |
| BTCommAdapterIndy.....                     | 29       | JMSCorrelationID.....      | 42       |
| BTConnection.....                          | 46       | JMSDeliveryMode.....       | 42       |
| Bug reports.....                           | 80       | JMSExpiration.....         | 42       |
| CheckHeartbeat.....                        | 51       | JMSMessageId.....          | 43       |
| Conditional symbols for unit test projects |          | JMSPriority.....           | 42       |
| .....                                      | 67       | JMSReplyTo.....            | 42f.     |
| connect.accept-version.....                | 49       | JMSTimestamp.....          | 42       |
| connect.heart-beat.....                    | 49       | Lazarus.....               | 8        |
| connect.host.....                          | 49       | Limitations.....           | 13, 73   |
| Connection.....                            | 30       | Linux.....                 | 80       |
| Connection URL.....                        | 30       | Logging.....               | 64       |
| ConnectionFactory.....                     | 29       | LoggingHelper.....         | 64       |
| ConnectTimeout.....                        | 13       | Message Consumer.....      | 38       |
| ConsumerTool.....                          | 54       | Message Producer.....      | 37       |
| CreateDurableSubscriber.....               | 40       | message properties.....    | 73       |
| CreateObjectMessage.....                   | 46       | MessageTransformer.....    | 46       |
| credentials.....                           | 62       | Multi threading.....       | 73       |
| Destination.....                           | 35       | multiple destinations..... | 73       |
| DISCONNECT Receipt.....                    | 27       | NativeXml.....             | 45       |
| DUnit.....                                 | 8, 61    | Object Message.....        | 45       |
| EIllegalStateException.....                | 76       | OmniXML.....               | 45       |
| Enables tests for experimental / optional  |          | OpenSSL.....               | 66, 69f. |
| units.....                                 | 67       | point-to-point.....        | 35       |
| experimental features.....                 | 80       | ProducerTool.....          | 56       |
| Failover Support.....                      | 24       | Programming Model.....     | 14       |
| FPCUnit.....                               | 8, 61    | publish and subscribe..... | 35       |
| Free Pascal.....                           | 8        | Queue.....                 | 35       |
| HABARI_LOGGING.....                        | 64, 66   | Receive.....               | 39       |
| HABARI_RAW_TRACE.....                      | 11       | ReceiveHeartbeat.....      | 51       |
| HABARI_SSL_SUPPORT.....                    | 66, 70   | ReceiveNoWait.....         | 39       |
| HABARI_TCP_KEEPALIVE.....                  | 67       | SamplePojo.....            | 46       |
| HABARI_TEST_OPTIONAL_UNITS.....            | 67       | Selector.....              | 73       |
| HABARI_TEST_SYNAPSE.....                   | 67       | Selectors.....             | 44       |
| HABARI_TEST_USE_MGMT_API.....              | 67       | SEND Receipt.....          | 27       |
| HABARI_USE_INTERCEPT.....                  | 11, 67   | SendHeartbeat.....         | 50       |
| HABARI_USE_INTERCEPT.....                  | 11       | Session.....               | 30       |
| IdInterceptSimLog.....                     | 67       | SetDefaultAdapter.....     | 70       |
| IHeartbeat.....                            | 50       | SetTransformer.....        | 46       |
| IMessageProducer.....                      | 46       | SimpleLogger.....          | 65       |
| IMQConsumer.....                           | 10       | SSL.....                   | 80       |
| IMQContext.....                            | 9        | Stomp 1.2.....             | 49       |
| IMQProducer.....                           | 9        | stomp+ssl.....             | 69       |
| Internet Direct (Indy).....                | <b>8</b> | subscribe receipt.....     | 26f.     |

|                            |                   |                          |        |
|----------------------------|-------------------|--------------------------|--------|
| Support.....               | 80                | Topic.....               | 36     |
| Synapse.....               | <b>8</b> , 13, 61 | TopicSubscriber.....     | 40     |
| synchronous receive.....   | 73                | Transacted Sessions..... | 32, 74 |
| TBTCommAdapterIndySSL..... | 69                | transactions.....        | 73     |
| TCP.....                   | 73                | Unit Tests.....          | 61     |
| tcp.keepalive.....         | 24                | virtual host.....        | 49     |
| Test destinations.....     | 62                | .receipt.....            | 27     |
| Throughput test.....       | 60                |                          |        |

## Table Index

|  |    |
|--|----|
| Table 1: Communication Adapters.....                     | 13 |
| Table 2: Failover Transport Options.....                 | 25 |
| Table 3: Session creation parameters.....                | 32 |
| Table 4: Message Transformer Implementations.....        | 45 |
| Table 5: Example Applications (in alphabetic order)..... | 52 |
| Table 6: ConsumerTool Command Line Options.....          | 54 |
| Table 7: ProducerTool Command Line Options.....          | 56 |
| Table 8: Throughput Test Tool Command Line Options.....  | 60 |
| Table 9: Communication Adapters with SSL Support.....    | 69 |

## Illustration Index

|  |    |
|--|----|
| Illustration 1: Programming Model.....                       | 14 |
| Illustration 2: Connection configuration dialog example..... | 53 |
| Illustration 3: ConsumerTool demo application.....           | 55 |
| Illustration 4: ProducerTool demo application.....           | 56 |
| Illustration 5: Performance Test Application.....            | 58 |
| Illustration 6: Throughput test tool output.....             | 60 |