



Getting started with

Habari Client for RabbitMQ

Version 6.1

LIMITED WARRANTY

No warranty of any sort, expressed or implied, is provided in connection with the library, including, but not limited to, implied warranties of merchantability or fitness for a particular purpose. Any cost, loss or damage of any sort incurred owing to the malfunction or misuse of the library or the inaccuracy of the documentation or connected with the library in any other way whatsoever is solely the responsibility of the person who incurred the cost, loss or damage. Furthermore, any illegal use of the library is solely the responsibility of the person committing the illegal act.

Trademarks

Habari is a trademark or registered trademark of Michael Justin in Germany and/or other countries. Android is a trademark of Google Inc. Use of this trademark is subject to Google Permissions. The Android robot is reproduced or modified from work created and shared by Google and used according to terms described in the Creative Commons 3.0 Attribution License. Embarcadero, the Embarcadero Technologies logos and all other Embarcadero Technologies product or service names are trademarks, service marks, and/or registered trademarks of Embarcadero Technologies, Inc. and are protected by the laws of the United States and other countries. IBM and WebSphere are trademarks of International Business Machines Corporation in the United States, other countries, or both. HornetQ, WildFly, JBoss and the JBoss logo are registered trademarks or trademarks of Red Hat, Inc. Mac OS is a trademark of Apple Inc., registered in the U.S. and other countries. Oracle, WebLogic and Java are registered trademarks of Oracle and/or its affiliates. Pivotal, RabbitMQ and the RabbitMQ logo are trademarks and/or registered trademarks of GoPivotal, Inc. in the United States and/or other countries. Other brands and their products are trademarks of their respective holders.

Errors and omissions excepted. Specifications subject to change without notice.

Contents

Broker-specific information.....	7
Installation.....	8
Requirements.....	8
Development Environment.....	8
TCP/IP Communication Library.....	8
Installation steps.....	8
Simplified API introduced in version 6.0.....	9
New interface types.....	9
IMQContext interface.....	9
IMQProducer interface.....	9
IMQConsumer interface.....	10
Source code example.....	10
Breaking changes in version 6.0.....	11
Removed conditional symbol HABARI_RAW_TRACE.....	11
Removed support for asynchronous message receive.....	11
Communication Adapters.....	12
Introduction.....	12
Configuration of communication adapters.....	12
Registration of communication adapter class.....	12
Available communication adapters.....	13
Limitations of the Synapse communication adapter class.....	13
The Programming Model.....	14
Tutorials.....	15
Quick Start Tutorial.....	15
Setting up the project.....	15
Adding code to the project.....	15
Run the demo.....	17
Check for memory leaks.....	17
Tutorial source code.....	17
Map Message Tutorial.....	18
Setting up the project.....	18
Adding code to the project.....	18
Run the demo.....	20
Map Message Conversion with Apache ActiveMQ.....	20
Tutorial source code.....	20
Connection Factory.....	21
Overview.....	21
Creation and configuration.....	21
Connection URL parameters.....	23
Heart-beating Support.....	23

TCP Keep-Alive (only supported with Indy).....	23
Failover Support.....	23
Failover Transport Options.....	24
Receipt Support.....	24
SUBSCRIBE Receipt.....	25
UNSUBSCRIBE Receipt.....	25
SEND Receipt.....	26
DISCONNECT Receipt.....	26
Connections and Sessions.....	27
Connections use Stomp 1.2 by default.....	27
Step-by-Step Example.....	27
Overview.....	27
Add required units.....	27
Creating a new Connection.....	28
Connection URL Parameters.....	28
Creating a Session.....	28
Using the Session.....	29
Closing a Connection.....	29
Session types overview.....	29
Transacted Sessions.....	30
Create a transacted session.....	30
Send messages.....	31
Committing a transaction.....	31
Rolling back a transaction.....	31
Transacted message acknowledgement.....	32
Destinations.....	33
Introduction.....	33
Create a new Destination.....	33
Queues.....	33
Topics.....	34
Producer and Consumer.....	35
Message Producer.....	35
Message Consumer.....	35
Message Selector.....	35
Synchronous Receive.....	36
Durable Subscriptions.....	37
Description.....	37
Creation.....	37
Temporary Queues.....	38
Introduction.....	38
Library Support.....	38
Resource Management.....	38
Message Options.....	39

Standard Properties	39
Properties for outgoing messages.....	39
Properties for incoming messages.....	39
Reserved property names	40
Examples.....	40
Prefix for custom headers.....	41
Selectors	41
Supported message brokers.....	41
Object Messages	42
Introduction	42
Object Serialization.....	42
Message Transformers	42
Memory Management.....	43
Assign a Message Transformer.....	43
Create and Send an ObjectMessage.....	43
Complete Example using NativeXml.....	44
Stomp 1.2	46
Connection configuration	46
Specification.....	47
Sending heart-beat signals	47
Checking for incoming heartbeats	48
Reading server-side heartbeats	48
Example Applications	49
Shared units for demo projects	50
ConsumerTool	51
Examples.....	52
ProducerTool	53
Examples.....	53
Performance test	55
Throughput test	57
Examples.....	57
Unit Tests	58
Introduction	58
Test project configuration	58
Logging.....	58
Raw message logging.....	58
Optional units.....	58
Synapse communication adapter.....	58
Test units	58
Test execution	59
Requirements.....	59
Test destinations.....	59
STOMP 1.2	60
Logging with SLF4P	61
Introduction	61

IDE and project configuration	61
Delphi.....	61
Lazarus.....	61
LoggingHelper unit	61
Conditional Symbols	63
Caution	63
Conditional symbols for release builds	63
HABARI_ALLOW_UNKNOWN_URL_PARAMS.....	63
HABARI_LOGGING.....	63
HABARI_SSL_SUPPORT.....	63
HABARI_TCP_KEEPALIVE.....	64
HABARI_USE_INTERCEPT.....	64
Conditional symbols for unit test projects	64
TEST_OPTIONAL_UNITS.....	64
HABARI_TEST_SYNAPSE.....	64
HABARI_TEST_USE_MGMT_API.....	64
SSL/TLS Support	66
SSL communication adapter classes	66
Mixed Use.....	66
SSL configuration.....	66
Indy SSL Demo	66
Notes.....	67
Example output.....	67
Support	68
Useful Units	69
BTStreamHelper unit	69
BTJavaPlatform unit	69
Library Limitations	70
MessageConsumer	70
How do I implement synchronous receive from multiple destinations?.....	70
Message properties	70
Only string data type supported by Stomp.....	70
Multi threading	70
Free Pascal specific restrictions	71
Broker-specific limitations	71
Transacted Sessions.....	71
Other broker specific limitations.....	71
Frequently Asked Questions	72
Technical questions	72
Why am I getting 'undeclared identifier IndyTextEncoding_UTF8'?.....	72
Why am I getting 'Found no matching consumer' errors?.....	72
Online Resources	74
Third-party libraries	74

Internet Direct (Indy).....	74
SLF4P.....	74
SuperObject.....	74
Synapse.....	74
Specifications.....	75
Online articles.....	75
Online Videos.....	76
Support.....	77
Bug reports and support inquiries.....	77
Advanced support.....	77
Broker-specific notes.....	78
Minimum supported broker version.....	78
Online resources.....	78
Message type detection.....	78
Prefetch count.....	79
Destination types.....	79
Header properties.....	79
Auto-delete queues.....	80
Creation of an auto-delete queue.....	80
Sending a message to the auto-delete queue.....	80
Queues with x-max-priority.....	80
Creation of the queue.....	81
Sending a message to the queue.....	81
Hint: check the broker log.....	81
Temporary queues.....	81
Special character encoding in STOMP headers.....	81
Durable subscriptions with RabbitMQ.....	83
Description.....	83
Creation.....	83
Deletion.....	84
Test tool example.....	84
Index.....	85

Broker-specific information

For broker-specific notes, please read chapter Broker-specific notes on page 78 ff.

Installation

Requirements

Development Environment

- **Embarcadero Delphi** 2009 Update 4 or higher
- or -
- **Free Pascal** 3.0.4 or higher

Lazarus 1.8 or newer is required to run the **FPCUnit** test suite. The DUnit test suite and the GUI demo applications require Delphi 2009 for compilation.

TCP/IP Communication Library

- **Internet Direct (Indy) 10.6** (recommended)
- or -
- **Synapse** Release 40¹

Installation steps

The installer application will guide you through the installation process.

By default Habari Client for RabbitMQ will be installed in the folder

C:\Users\Public\Documents\Habarisoft\habari-<broker>-6.1

where broker is for example 'activemq' or 'rabbitmq' depending on your version.

1 Only release 40 of Ararat Synapse is used for Habari Client library development and tests

Simplified API introduced in version 6.0

New interface types

The new API in Habari Client libraries 6.0 is based on three new interfaces which reduce the amount of client code:

- IMQContext
- IMQProducer
- IMQConsumer

IMQContext interface

A IMQContext object encapsulates both the IConnection and the ISession object of the classic API. The connection factory interface contains new methods to create IMQContext objects:

Code example

```
function CreateContext: IMQContext; overload;
function CreateContext(const AcknowledgeMode:
    TAcknowledgementMode): IMQContext; overload;
function CreateContext(const Username, Password: string):
    IMQContext; overload;
function CreateContext(const Username, Password: string;
    const AcknowledgeMode: TAcknowledgementMode):
    IMQContext; overload;
```

The IMQContext provides methods to create messages, producer and consumer objects, destinations (queues, topics, temporary queues, temporary topics, durable subscribers and so forth), and for transaction control (commit, rollback).

IMQProducer interface

A IMQProducer object provides methods to produce and send messages to the broker. As a shortcut, a method allows to send text or bytes messages without creating IMessage or IBytesMessage object by providing the text or bytes as a parameter.

Code example

```
function Send(const Destination: IDestination;
```

10 Habari Client for RabbitMQ 6.1

```
const Body: string): IMQProducer; overload;
function Send(const Destination: IDestination;
              const AMessage: IMessage): IMQProducer; overload;
```

IMQConsumer interface

An IMQConsumer object provides methods to consume messages from the broker.

The following example is taken from the unit tests. It uses the new API to create and send a text message to a broker queue destination, and then receives the message from this queue.

Source code example

Code example

```
procedure TNewApiTests.TestSendMessage;
var
  Context: IMQContext;
  Destination: IQueue;
  Producer: IMQProducer;
  Consumer: IMQConsumer;
  TextMessage: ITextMessage;
begin
  Context := Factory.CreateContext;
  Destination := Context.CreateQueue(GetQueueName);

  Producer := Context.CreateProducer;
  Producer.Send(Destination, 'Hello World');

  Consumer := Context.CreateConsumer(Destination);
  TextMessage := Consumer.Receive(2500) as ITextMessage;

  CheckEquals('Hello World', TextMessage.Text);
  Context.Close;
end;
```

Breaking changes in version 6.0

Removed conditional symbol **HABARI_RAW_TRACE**

For detailed logging of network traffic, you may use the conditional symbol `HABARI_USE_INTERCEPT`.

Removed support for asynchronous message receive

The following methods and properties are no longer available:

```
function CreateConsumer(const Destination: IDestination;
    const MessageSelector: string; const NoLocal: Boolean;
    const MessageListener: IMessageListener): IMessageConsumer;
```

```
IMessageConsumer = interface
    ...
    function GetMessageListener: IMessageListener;
    procedure SetMessageListener(const Value: IMessageListener);

    property MessageListener: IMessageListener read GetMessageListener write
        SetMessageListener;
    ...
end interface
```

Communication Adapters

Introduction

Habari Client for RabbitMQ uses communication adapters as an abstraction layer for the TCP/IP library. All connections create their own internal instance of the adapter class.

Configuration of communication adapters

No configuration is required for the communication adapters. Applications specify communication and connection options in URL parameters or connection class properties or connection factory settings.

Registration of communication adapter class

A communication adapter implementation can be prepared for usage by simply adding its Delphi unit to the project.

Code example

```
program ClientUsingIndy;

uses
  BTCommAdapterIndy, // use Internet Direct (Indy)
  BTConnectionFactory, BTJMSInterfaces,
  SysUtils;
...
```

Behind the scenes, the communication adapter class will register itself with the communication adapter manager in the `BTAdapterRegistry` unit.

Default adapter class

Applications typically use only one of the available communication adapter classes for all connections.

The library allows to register two or more adapter classes and switch at run-time, using methods in the adapter registry in unit `BTAdapterRegistry` - this feature is mainly for tests and demonstration purposes.

If more than one communication adapter is in the project, the **first** adapter class in the list will be the default adapter class. Example:

Code example

```

program ClientUsingIndyOrSynapse;

uses
  BTCommAdapterIndy, // use Internet Direct (Indy) as default adapter class
  BTCommAdapterSynapse, // and register the Synapse adapter class
  BTConnectionFactory, BTJMSInterfaces,
  SysUtils;
...

```

The default adapter class can be changed at run-time by setting the adapter class either by its name or by its class type.

Available communication adapters

The library includes two adapter classes for TCP/IP libraries, one for Indy (Internet Direct) and one for Synapse.

Adapter Class	Unit
TBTCommAdapterIndy	BTCommAdapterIndy
TBTCommAdapterSynapse	BTCommAdapterSynapse

Table 1: Communication Adapters

Limitations of the Synapse communication adapter class

- The Synapse library does not support the `ConnectTimeout` property in synchronous socket operation mode, as connect timeouts are handled by the operating system. Indy uses a background thread to abort the connect operation.²
- Release 40 of Ararat Synapse is used for Habari Client library development and tests. This is the last announced release, dated April 24, 2012. If you use a newer release of Ararat Synapse, please let me know if you encounter any API incompatibilities or other problems.

² <http://www.ararat.cz/synapse/doku.php/public:howto:connecttimeout>

The Programming Model

Habari Client libraries use a programming model which is based on message producers and message consumers, sessions, connections and connection factories.

The basic API is the same for all library versions to allow easy migration between supported message brokers (with the exception of broker-specific features).




Illustration 1: Programming Model

Tutorials

Quick Start Tutorial

This tutorial provides a very simple and quick introduction to Habari Client for RabbitMQ by walking you through the creation of a simple "Hello World" application. Once you are done with this tutorial, you will have a general knowledge of how to create and run Habari applications.

This tutorial takes less than 10 minutes to complete.

Setting up the project

To create a new project:

1. Start the Delphi IDE.
2. In the IDE, choose File > New > VCL Forms Application – Delphi
3. Choose Project > Options ... to open the Project Options dialog
4. In the options tree on the left, select 'Delphi Compiler'
5. Add the source directory of Habari Client for RabbitMQ and the Synapse source directory to the 'Search path'
6. Choose Ok to close the Project Options dialog
7. Save the project as HelloMQ

Now the project is created and saved.

You should see the main form in the GUI designer now.

Adding code to the project

To use the Habari Client for RabbitMQ library, you need to add the required units to the source code.

8. Switch to Code view (F12)
9. Add the required units to the interface uses list:

Code example

```
uses
  BTConnectionFactory,
  BTJMSInterfaces,
```

16 Habari Client for RabbitMQ 6.1

```
BTCommAdapterSynapse,  
// auto-generated unit references  
Windows, Messages, SysUtils, ...
```

10. Compile and save the project.

11. Switch to Design view (F12), go to the Tool palette (Ctrl+Alt+P) and select TButton, add a Button to the form.

12. Double click on the new button to jump to the Button Click handler

13. Add the following code to send the message:

Code example

```
procedure TForm1.Button1Click(Sender: TObject);  
var  
    Factory: IConnectionFactory;  
    Connection: IConnection;  
    Session: ISession;  
    Destination: IDestination;  
    Producer: IMessageProducer;  
begin  
    Factory := TBConnectionFactory.Create('stomp://localhost');  
    Connection := Factory.CreateConnection;  
    Connection.Start;  
  
    Session := Connection.CreateSession(False, amAutoAcknowledge);  
    Destination := Session.CreateQueue('HelloMQ');  
    Producer := Session.CreateProducer(Destination);  
    Producer.Send(Session.CreateTextMessage('Hello world!'));  
  
    Connection.Close;  
end;
```

14. Add a second button and double click on the new button to jump to the Button Click handler

15. Add the following code to receive and display the message:

Code example

```
procedure TForm1.Button2Click(Sender: TObject);  
var  
    Factory: IConnectionFactory;  
    Connection: IConnection;  
    Session: ISession;  
    Destination: IDestination;  
    Consumer: IMessageConsumer;  
    Msg: ITextMessage;  
begin  
    Factory := TBConnectionFactory.Create('stomp://localhost');  
    Connection := Factory.CreateConnection;  
    Connection.Start;  
  
    Session := Connection.CreateSession(False, amAutoAcknowledge);
```



```

Destination := Session.CreateQueue('HelloMQ');
Consumer := Session.CreateConsumer(Destination);
Msg := Consumer.Receive(1000) as ItextMessage;

if Assigned(Msg) then
    ShowMessage(Msg.Text)
else
    ShowMessage('Error: no message received');

Connection.Close;
end;

```

16. Compile and save the project

Run the demo

- Launch the message broker
- Start the application
- Click on Button 1 to send the message to the queue
- Click on Button 2 to receive the message and display it

You can run two instances of the application at the same time, and also on different computers if the IP address of the message broker is used instead of localhost.

Check for memory leaks

To verify that the program does not cause memory leaks, insert a line in the project file HelloMQ.dpr:

Code example

```

program HelloMQ;

uses
    Forms,
    Unit1 in 'Unit1.pas' {Form1};

{$R *.res}

begin
    ReportMemoryLeaksOnShutdown := True; // check for memory leaks
    Application.Initialize;
    Application.MainFormOnTaskbar := True;
    Application.CreateForm(TForm1, Form1);
    Application.Run;
end.

```

Tutorial source code

The tutorial source code is included in the demo folder. It does not include a .proj file so you still need to add the Habari and Synapse source paths to the project options.

Map Message Tutorial

This tutorial provides a quick introduction to Habari Client for RabbitMQ by walking you through the creation of a simple map message exchange application.

This tutorial takes less than 10 minutes to complete.

Setting up the project

To create a new project:

1. Start the Delphi IDE.
2. In the IDE, choose File > New > VCL Forms Application – Delphi
3. Choose Project > Options ... to open the Project Options dialog
4. In the options tree on the left, select 'Delphi Compiler'
5. Add the source directory of Habari source, the Habari source\optional, and the Synapse source directory to the 'Search path'
6. Choose OK to close the Project Options dialog
7. Save the project as HelloMapMessage

Now the project is created and saved.

You should see the main form in the GUI designer now.

Adding code to the project

To use the Habari Client for RabbitMQ library, you need to add the required units to the source code.

8. Switch to Code view (F12)
9. Add the required units to the interface uses list:

Code example

```
uses
  BTConnectionFactory, BTJMSInterfaces, BTCommAdapterSynapse, BTConnection,
  BTMessageTransformerXMLMapDocument, BTSerialIntf, BTTypes,
  // auto-generated unit references
  Windows, Messages, SysUtils, ...
```

10. Compile and save the project.
11. Switch to Design view (F12), go to the Tool palette (Ctrl+Alt+P) and add a TMemo and a TButton to the form.
12. Double click on the new button to jump to the Button Click handler
13. Add the following code to send the message:

Code example

```

procedure TForm1.Button1Click(Sender: TObject);
var
  Factory: IConnectionFactory;
  Connection: IConnection;
  Session: ISession;
  Destination: IDestination;
  Producer: IMessageProducer;
  MapMessage: IMapMessage;
  Key: string;
begin
  Factory := TBTFConnectionFactory.Create('stomp://localhost');
  Connection := Factory.CreateConnection;
  SetTransformer(Connection, TBTFMessageTransformerXMLMapDocument.Create(nil));
  Connection.Start;

  Session := Connection.CreateSession(False, amAutoAcknowledge);
  Destination := Session.CreateQueue('HelloMapMessage');
  Producer := Session.CreateProducer(Destination);

  MapMessage := Session.CreateMapMessage;
  MapMessage.SetString('DateTimeToStr(Now)', DateTimeToStr(Now));
  MapMessage.SetString('ParamStr(0)', ParamStr(0));

  Producer.Send(MapMessage);

  Memo1.Lines.Append('Sent:');
  for Key in MapMessage.GetMapNames do
  begin
    Memo1.Lines.Append(Key + '=' + MapMessage.GetString(Key));
  end;

  Connection.Close;
end;

```

14. Add a second button and double click on the new button to jump to the Button Click handler

15. Add the following code to receive and display the message:

Code example

```

procedure TForm1.Button2Click(Sender: TObject);
var
  Factory: IConnectionFactory;
  Connection: IConnection;
  Session: ISession;
  Destination: IDestination;
  Consumer: IMessageConsumer;
  MapMessage: IMapMessage;
  Key: string;
begin
  Factory := TBTFConnectionFactory.Create('stomp://localhost');
  Connection := Factory.CreateConnection;
  SetTransformer(Connection, TBTFMessageTransformerXMLMapDocument.Create(nil));
  Connection.Start;

```

20 Habari Client for RabbitMQ 6.1

```
Session := Connection.CreateSession(False, amAutoAcknowledge);
Destination := Session.CreateQueue('HelloMapMessage'
  + '?transformation=' + BTSerialIntf.TRANSFORMER_ID_MAP_XML);
Consumer := Session.CreateConsumer(Destination);

MapMessage := Consumer.Receive(1000) as IMapMessage;

if Assigned(MapMessage) then
begin
  Mem1.Lines.Append('Received:');
  for Key in MapMessage.GetMapNames do
  begin
    Mem1.Lines.Append(Key + '=' + MapMessage.GetString(Key));
  end;
end;

Connection.Close;
end;
```

16. Compile and save the project

Run the demo

- Launch the message broker
- Start the application
- Click on Button 1 to send the map message to the queue
- Click on Button 2 to receive the map message and display it

You can run two instances of the application at the same time, and also on different computers if the IP address of the message broker is used instead of localhost.

Map Message Conversion with Apache ActiveMQ

Note: if you send and receive map messages using the library, message brokers will receive them as simple STOMP text messages with a special header property "transformation" which is set to the value JMS_MAP_XML (or JMS_MAP_JSON if you use a JSON based map transformer class).

Most message brokers will not perform any special processing of these STOMP messages. A notable exception is Apache ActiveMQ: if the broker receives a STOMP message with the JMS_MAP_XML or JMS_MAP_JSON transformation header, it will convert the message internally to a 'native' JMS MapMessage. This allows Java clients to receive the message sent from the Delphi application as a MapMessage without the need to parse a XML body.

Habari Client map message transformers only support string properties.

Tutorial source code

The tutorial source code is included in the demo folder. It does not include a .proj file so you still need to add the Habari and Synapse source paths to the project options.

Connection Factory

Overview

A connection factory is an object which holds all information required for the creation of a connection objects.

A factory instance is created and configured only once. It then may be used to create actual connection objects when needed. For example, a worker thread may create the connection factory once at program start-up and use it to create a new connection object whenever a connection failure occurred.

Creation and configuration

The code example below shows a helper function which creates a connection factory, and returns it using the interface type `IConnectionFactory`.

The factory will be freed automatically when there are no more references to it.

Code example

```
function TExample.CreateConfiguredFactory: IConnectionFactory;
var
  Factory: IConnectionFactory;
begin
  // -----
  // create an instance
  // -----
  Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?
send.receipt=true');

  // -----
  // return the instance
  // -----
  Result := Factory;
end;
```

This code example is useful for most simple client applications. However, because the local factory variable is declared as `IConnectionFactory`, advanced configuration properties in the class `TBTConnectionFactory` such as `ClientID` and `SendTimeout` are not accessible.

To access them, declare the local factory with the class type as shown in the next example:

22 Habari Client for RabbitMQ 6.1

Code example

```
function TExample.CreateConfiguredFactory: IConnectionFactory;
var
  Factory: TBTCConnectionFactory;
begin
  // -----
  // create and assign to local variable
  // -----
  Factory := TBTCConnectionFactory.Create;

  // -----
  // additional configuration
  // -----

  Factory.BrokerURL := 'broker.example.com';
  Factory.UserName := 'guest';
  Factory.Password := 'guest';
  Factory.ClientID := 'myclientId';
  Factory.SendTimeout := 10000;
  Factory.ConnectTimeout := 10000; // Indy only

  // -----
  // return the configured factory
  // -----
  Result := Factory;
end;
```

Warning: if the method signature is changed to return the class TBTCConnectionFactory instead, a memory leak will occur.

Code example

```
function TExample.Run;
var
  F: IConnectionFactory;
  C: IConnection;
begin
  // -----
  // get a factory and use it to create a connection object
  // -----
  F := CreateConfiguredFactory;

  C := F.CreateConnection;

  // -----
  // start and use the connection
  // -----
  C.Start;
  ...
  // -----
  // close the connection
  // -----
  C.Close;
end;
```

Connection URL parameters

Heart-beating Support

STOMP 1.1 introduced heart-beating, its configuration is covered in the chapter Stomp 1.2

TCP Keep-Alive (only supported with Indy)

The library supports TCP keep-alive with an optional connection URL parameter, `tcp.keepalive`.

The parameter takes two arguments. On Linux, the first argument is the initial delay before the first keep-alive, the second argument specifies the interval (both values are in milliseconds). On the Windows platform, the values of these arguments are ignored and the operating system uses default values for initial delay³ and interval⁴, which can be modified in the registry.

Code example

```
Factory := TBTCConnectionFactory.Create('user', 'password', 'stomp://localhost?
tcp.keepalive=1000,1000');
```

Note	TCP keep-alive is currently only supported by the Indy communication adapter
Important	To enable TCP keep-alive, the project must be compiled with the conditional symbol <code>HABARI_TCP_KEEPALIVE</code>

Failover Support

The Failover transport layers reconnect logic on top of the Stomp transport.⁵

The Failover configuration syntax allows you to specify any number of composite URIs. The Failover transport randomly chooses one of the composite URI and attempts to establish a connection to it. If it does not succeed, a new connection is established to one of the other URIs in the list.

Example for a failover URI:

```
failover:(stomp://primary:61613,stomp://secondary:61613)
```

3 <http://technet.microsoft.com/en-us/library/cc957549.aspx>

4 <http://technet.microsoft.com/en-us/library/cc957548.aspx>

5 <http://activemq.apache.org/failover-transport-reference.html>

Failover Transport Options

Option Name	Default Value	Description
initialReconnectDelay	10	How long to wait before the first reconnect attempt (in ms)
maxReconnectDelay	30000	The maximum amount of time we ever wait between reconnect attempts (in ms)
backOffMultiplier	2.0	The exponent used in the exponential backoff attempts
maxReconnectAttempts	-1	-1 is default and means retry forever, 0 means don't retry (only try connection once but no retry) If set to > 0, then this is the maximum number of reconnect attempts before an error is sent back to the client
randomize	true	use a random algorithm to choose the the URI to use for reconnect from the list provided

Table 2: Failover Transport Options

Example URI:

```
failover:(stomp://localhost:61616,stomp://remotehost:61616)?
initialReconnectDelay=100&maxReconnectAttempts=10
```

Code example

```
Factory := TBTPConnectionFactory.Create('failover:(stomp://primary:61616,stomp://
localhost:61613)?maxReconnectAttempts=3&randomize=false') do
try
  Conn := Factory.CreateConnection;
  Conn.Start;
  ...
  Conn.Stop;
finally
  Conn.Close;
end;
```

Receipt Support

The STOMP standard supports receipt messages since version 1.0:

"Any client frame other than CONNECT may specify a *receipt* header with an arbitrary value. This will cause the server to acknowledge receipt of the frame

with a RECEIPT frame which contains the value of this header as the value of the *receipt-id* header in the RECEIPT packet."⁶⁷⁸

With Habari Client for RabbitMQ, client applications may configure receipt headers for the frame types listed below.

After the STOMP frame has been sent to the broker, the client library waits for the RECEIPT frame for a defined time, which may be configured per frame type. If the broker does not send a receipt within the time-out interval, the client library will raise an exception. If the client receives a receipt with the wrong receipt-id header, it will raise an exception.

Receipt Support Parameters

STOMP frame	Parameter	Example URL
SUBSCRIBE	subscribe.receipt	stomp://localhost?subscribe.receipt=true
UNSUBSCRIBE	subscribe.receipt	stomp://localhost? unsubscribe.receipt=true
SEND	send.receipt	stomp://localhost?send.receipt=true
DISCONNECT	disconnect.receipt	stomp://localhost?disconnect.receipt=tru

SUBSCRIBE Receipt

To request server receipts for SUBSCRIBE frames, use the optional connection URL parameter, `subscribe.receipt`.

Code example

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?
subscribe.receipt=true');
```

If the broker does not send a receipt within the time-out interval, the client library will raise an exception.

UNSUBSCRIBE Receipt

To request server receipts for UNSUBSCRIBE frames, use the optional connection URL parameter, `unsubscribe.receipt`.

6 <https://stomp.github.io/stomp-specification-1.0.html>

7 https://stomp.github.io/stomp-specification-1.1.html#Header_receipt

8 https://stomp.github.io/stomp-specification-1.2.html#Header_receipt

Code example

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?unsubscribe_receipt=true');
```

If the broker does not send a receipt within the time-out interval, the client library will raise an exception.

SEND Receipt

To request server receipts for SEND frames, use the optional connection URL parameter, `send_receipt`.

Code example

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?send_receipt=true');
```

If the broker does not send a receipt within the time-out interval, the client library will raise an exception.

Note: for additional reliability, the client can use transactional send (see section "Transacted Sessions").

DISCONNECT Receipt

To request server receipts for DISCONNECT frames, use the optional connection URL parameter, `disconnect_receipt`.

Code example

```
Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost?disconnect_receipt=true');
```

Without this parameter, the client will disconnect the socket connection immediately after sending the DISCONNECT frame to the broker.

With `disconnect_receipt=true`, the client will send the DISCONNECT frame and then wait for the broker receipt frame. If the broker does not answer, the client library will raise an exception. The client application should treat its messages as undelivered.

Note: for additional reliability, the client can use transactional send (see section "Transacted Sessions"), and message receipts (see section "SEND Receipt").

Connections and Sessions

Connections use Stomp 1.2 by default

Connections use Stomp 1.2 by default since

- Habari Client for Apache ActiveMQ 5.1
- Habari Client for Apache Artemis 5.1
- Habari Client for RabbitMQ 5.1

With OpenMQ, the library still uses Stomp 1.0.

Stomp version may be specified by connection URL parameters. The default protocol version is defined in the BTBrokerConsts unit.

Step-by-Step Example

Overview

This example will send a single message to a destination queue (ExampleQueue).⁹

Add required units

Three units are required for this example

- a communication adapter unit (e. g. BTCommAdapterIndy)
- a connection factory unit (BTConnectionFactory)
- the unit containing the interface declarations (BTJMSInterfaces)

The SysUtils unit is necessary for the exception handling.

Code example

```
program SendOneMessage;  
  
{ $APPTYPE CONSOLE }  
  
uses
```

⁹ Compatibility note: non-existing queues are created automatically by the broker – with the exception of Artemis and HornetQ which require them to be configured before usage

```
BTCommAdapterIndy,  
BTConnectionFactory,  
BTJMSInterfaces,  
SysUtils;  
...
```

Creating a new Connection

New connections are created by calling the `CreateConnection` method of a connection factory.

Code example

```
var  
  Factory: IConnectionFactory;  
  Connection: IConnection;  
  ...  
begin  
  Factory := TBTConnectionFactory.Create('user', 'password', 'stomp://localhost');  
  Connection := Factory.CreateConnection;  
  ...
```

- For connection factory creation and configuration options please see chapter "[Creation and configuration](#)".
- Since `IConnection` is an interface type, the connection instance will be destroyed automatically if there are no more references to it in the program.

Connection URL Parameters

Connection URL parameters are documented in chapter "[Connection URL parameters](#)" and in chapter "Stomp 1.2".

Creating a Session

To create the communication session,

- declare a variable of type `ISession`
- use the helper method `CreateSession` of the connection, and specify the acknowledgment mode

Please check the API documentation for the different session types and acknowledgement modes.

Since `ISession` is an interface type, the session instance will be destroyed automatically if there are no more references to it in the program.

Code example

```
Session := Connection.CreateSession(False, amAutoAcknowledge);
```

Using the Session

The Session variable is ready to use now. Destinations, producers and consumers will be covered in the next chapters.

Code example

```
Destination := Session.CreateQueue('ExampleQueue');
Producer := Session.CreateProducer(Destination);
Producer.Send(Session.CreateTextMessage('This is a test message'));
```

Closing a Connection

Finally, the application closes the connection. The client will disconnect from the message broker. Closing a connection also implicitly closes all open sessions.

Code example

```
finally
    Connection.Close;
end;
end.
```

Note: Close will be called automatically if the connection is destroyed. But because unclosed connections use resources, Close should be called when the connection is no longer needed. When logging is enabled, the connection class will also log a message when a connection is destroyed without calling Close.

Session types overview

The table below shows the supported parameter combinations for the Connection.CreateSession method and their effect on the session transaction and acknowledgment features.

Parameters	Client MUST acknowledge message receipt ¹⁰	Transaction support for		STOMP Version
		Send	Ack	

¹⁰ https://stomp.github.io/stomp-specification-1.2.html#SUBSCRIBE_ack_Header

CreateSession(False, amAutoAcknowledge)	No	-	-	1.0
CreateSession(False, amClientAcknowledge)	Yes (cumulative effect)	-	-	1.0
CreateSession(False, amClientIndividual)	Yes	-	-	1.2
CreateSession(True, amAutoAcknowledge)	No	✓	-	1.0
CreateSession(True, amClientAcknowledge)	Yes (cumulative effect)	✓	✓ ①	1.0
CreateSession(True, amClientIndividual)	Yes	✓	✓ ①	1.2
CreateSession(True, amTransactional)	No	✓	-	1.0

Table 3: Session creation parameters

① – not supported by ActiveMQ Artemis

Transacted Sessions

A session may be specified as transacted. Each transacted session supports a single series of transactions.

Each transaction groups a set of message sends into an atomic unit of work.

A transaction is completed using either its session's Commit method or its session's Rollback method. The completion of a session's current transaction automatically begins the next. The result is that a transacted session always has a current transaction within which its work is done.

Create a transacted session

To create a transacted session, set the parameter of CreateSession to amTransactional as shown in the code example

Code example

```
Session := Connection.CreateSession(amTransactional);
```

or (using the older API version)

Code example

```
Session := Connection.CreateSession(True, amTransactional);
```

This code will automatically start a new transaction for this session.

Send messages

Now send messages using the transacted session.

Code example

```
Destination := Session.CreateQueue('testqueue');
Producer := Session.CreateProducer(Destination);
Producer.Send(Session.CreateTextMessage('This is a test message'));
```

Committing a transaction

If your client code has successfully sent its messages, the transaction must be committed to make the messages visible on the destination.

Code example

```
// send messages ...

finally
  // commit all messages
  Session.Commit;
end;
```

Note: committing a transaction automatically starts a new transaction

Rolling back a transaction

If your client code runs wants to undo the sending of its messages, the transaction may be rolled back, and the messages will not become visible on the destination.

Code example

```
// send messages ...

except
  ...
  // error!
  Session.Rollback;
  ...
end;
```

Note: rolling back a transaction automatically starts a new transaction. A transacted session will be rolled back automatically if the connection is closed.

Transacted message acknowledgement

Some library versions (see table "Communication Adapters" on page 13) support transactions also for the acknowledgement of received messages.

When a transaction is rolled back or the connection is closed without a commit, messages which have been acknowledged after the transaction start will return to unacknowledged state.

Code example

```
// receive in a transacted session
Session := Connection.CreateSession(True, amClientAcknowledge);
Queue := Session.CreateQueue(GetQueueName);
Consumer := Session.CreateConsumer(Queue);
Msg := Consumer.Receive(1000);

// process the message
...

// acknowledge the message
Msg.Acknowledge;

...

// in case of errors, roll back all acknowledgements
Session.Rollback;
```

This is an experimental feature. It requires the STOMP 1.2 communication protocol.

Destinations

Introduction

The API supports two models:¹¹

1. point-to-point or queuing model
2. publish and subscribe model

In the point-to-point or queuing model, a producer posts messages to a particular queue and a consumer reads messages from the queue. Here, the producer knows the destination of the message and posts the message directly to the consumer's queue. It is characterized by following:

- Only one consumer will get the message
- The producer does not have to be running at the time the receiver consumes the message, nor does the receiver need to be running at the time the message is sent
- Every message successfully processed is acknowledged by the receiver

The publish/subscribe model supports publishing messages to a particular message topic. Zero or more subscribers may register interest in receiving messages on a particular message topic. In this model, neither the publisher nor the subscriber know about each other. A good metaphor for it is anonymous bulletin board. The following are characteristics of this model:

- Multiple consumers can get the message
- There is a timing dependency between publishers and subscribers. The publisher has to create a subscription in order for clients to be able to subscribe. The subscriber has to remain continuously active to receive messages, unless it has established a durable subscription. In that case, messages published while the subscriber is not connected will be redistributed whenever it reconnects.

Create a new Destination

Queues

A queue can be created using the `CreateQueue` method of the `Session`.

¹¹Java Message Service. (2007, November 21). In Wikipedia, The Free Encyclopedia. http://en.wikipedia.org/wiki/Java_Message_Service

Code example

```
Destination := Session.CreateQueue('foo');  
Consumer := Session.CreateConsumer(Destination);
```

The queue can then be used to send or receive messages using implementations of the `IMessageProducer` and `IMessageConsumer` interfaces. (See next chapter for an example)

Topics

A topic can be created using the `CreateTopic` method of the `Session`.

Code example

```
Destination := Session.CreateTopic('bar');  
Consumer := Session.CreateConsumer(Destination);
```

The topic can then be used to send or receive messages using implementations of the `IMessageProducer` and `IMessageConsumer` interfaces. (See next chapter for an example).

Producer and Consumer

Message Producer

A client uses a MessageProducer object to send messages to a destination. A MessageProducer object is created by passing a Destination object to a message-producer creation method supplied by a session.

Code example

```
Destination := Session.CreateQueue('foo');
Producer := Session.CreateProducer(Destination);
Producer.Send(Session.CreateTextMessage('Test message'));
```

A client can specify a default delivery mode, priority, and time to live for messages sent by a message producer. It can also specify the delivery mode, priority, and time to live for an individual message.

Message Consumer

A client uses a MessageConsumer object to receive messages from a destination. A MessageConsumer object is created by passing a Destination object to a message-consumer creation method supplied by a session.

Code example

```
Destination := Session.CreateQueue('foo');
Consumer := Session.CreateConsumer(Destination);
```

Message Selector

A message consumer can be created with a **message selector**¹².

A message selector allows the client to restrict the messages delivered to the message consumer to those that match the selector.

¹²The RabbitMQ message broker does not support message selectors

Synchronous Receive

A MessageConsumer offers a Receive method which can be used to consume exactly one message at a time.

Code example

```
while I < EXPECTED do
begin
  TextMessage := Consumer.Receive(1000) as ITextMessage;
  if Assigned(TextMessage) then
  begin
    Inc(I);
    TextMessage.Acknowledge;
    L.Info(Format('%d %s', [I, TextMessage.Text]));
  end;
end;
```

Receive and ReceiveNoWait

There are three different methods for synchronous receive:

- | | |
|-------------------------|--|
| Receive | The Receive method with no arguments will block (wait until a message is available). |
| Receive(Timeout) | The Receive method with a timeout parameter will wait for the given time in milliseconds. If no message arrived, it will return nil. |
| ReceiveNoWait | The ReceiveNoWait method will return immediately. If no message arrived, it will return nil. |

Durable Subscriptions

Description

If a client needs to receive all the messages published on a topic, including the ones published while the subscriber is inactive, it uses a durable `TopicSubscriber`.

The message broker retains a record of this durable subscription and insures that all messages from the topic's publishers are retained until they are acknowledged by this durable subscriber or they have expired.¹³

The combination of the `clientId` and durable subscriber name uniquely identifies the durable topic subscription.

After you restart your program and re-subscribe, the broker will know which messages you need that were published while you were away.

Creation

The `Session` interface contains the `CreateDurableSubscriber` method which creates a durable subscriber to the specified topic.

A durable subscriber `MessageConsumer` is created with a unique `clientId` and durable subscriber name.

Only **one** thread can be actively consuming from a given logical topic subscriber.

¹³ <http://download.oracle.com/javaee/5/api/javax/jms/TopicSession.html>

Temporary Queues

Introduction

“Temporary destinations (temporary queues or temporary topics) are proposed as a lightweight alternative in a scalable system architecture that could be used as unique destinations for replies. Such destinations have a scope limited to the connection that created it, and are removed on the server side as soon as the connection is closed.” (“Designing Messaging Applications with Temporary Queues”, by Thakur Thribhuvan ¹⁴)

Library Support

Temporary destinations are supported by

- ActiveMQ
- OpenMQ
- RabbitMQ

Resource Management

The session should be closed as soon as processing is completed so that TemporaryQueues will be deleted on the server side.

¹⁴ <http://onjava.com/pub/a/onjava/2007/04/10/designing-messaging-applications-with-temporary-queues.html>

Message Options

Standard Properties

The Apache ActiveMQ message broker supports some JMS standard properties in the STOMP adapter. These properties are based on the JMS specification of the Message interface.¹⁵

Habari Client libraries for other message brokers may support a subset of these standard properties.

Note: If your application makes use of these properties, your application depends on a broker-specific feature which is not guaranteed to be available in the STOMP adapter of other message brokers

Properties for outgoing messages

JMSCorrelationID	The correlation ID for the message.
JMSExpiration	The message's expiration value.
JMSDeliveryMode	Whether or not the message is persistent.
JMSPriority ¹⁶	The message priority level.
JMSReplyTo	The Destination object to which a reply to this message should be sent.

Properties for incoming messages

JMSCorrelationID	The correlation ID for the message.
JMSExpiration	The message's expiration value.
JMSDeliveryMode	Whether or not the message is persistent.
JMSPriority	The message priority level.

¹⁵ <http://download.oracle.com/javaee/5/api/javax/jms/Message.html>

¹⁶ Clients set the JMSPriority not directly, but either on the producer or as a parameter in the Send method

JMSTimestamp	The timestamp the broker added to the message.
JMSMessageId	The message ID which is set by the provider.
JMSReplyTo	The Destination object to which a reply to this message should be sent.

Reserved property names

Some headers names are defined by the Stomp specifications, and by broker-specific extensions of the Stomp protocol. These reserved Stomp header names can not be used as names for user defined properties.

Note The client library will raise an Exception if the application tries to send a message with a reserved property name.

Examples

- login
- passcode
- transaction
- session
- message
- destination
- id
- ack
- selector
- type
- content-length
- content-type
- correlation-id
- expires
- persistent
- priority
- reply-to
- message-id
- timestamp
- transformation
- client-id

- redelivered

Prefix for custom headers

A common practice to avoid name collisions is using a prefix for your own properties (example: **x-type** instead of **type**).

Selectors

Selectors are a way of attaching a filter to a subscription to perform content based routing. For more documentation on the detail of selectors see the reference on `javax.jmx.Message`¹⁷.

Supported message brokers

Message selectors are supported by

- Habari Client for ActiveMQ
Habari Client for Artemis
- Habari Client for OpenMQ

Code example

```
Consumer := Session.CreateConsumer(Destination, 'type='car' and color='blue');
```

All supported brokers allow supports string type properties and operations in selectors. ActiveMQ also allows integer properties and operations in selectors (see special note¹⁸).

17 <http://docs.oracle.com/javaee/5/api/javax/jms/Message.html>

18 <http://activemq.apache.org/selectors.html>

Object Messages

Introduction

Object Serialization

Object serialization is the process of saving an object's state to a sequence of bytes, as well as the process of rebuilding those bytes into a live object at some future time.¹⁹ In messaging applications, object serialization is required to transfer objects between clients, but also to store objects on the broker if they are declared persistent.

Message Transformers

Transformation	Message Type	Library	Unit
XML	ObjectMessage	OmniXML	BTMessageTransformerXMLOmni
XML	ObjectMessage	NativeXml	BTMessageTransformerXMLNative
XML	MapMessage	OmniXML	BTMessageTransformerXMLMapOmni
XML	MapMessage	NativeXml	BTMessageTransformerXMLMapNative
XML	MapMessage	IDocument	BTMessageTransformerXMLMapDocument
JSON	ObjectMessage	SuperObject	BTMessageTransformerJSONSuperObject
JSON	MapMessage	SuperObject	BTMessageTransformerJSONMapSuperObject

Table 4: Message Transformer Implementations

¹⁹ <http://www.oracle.com/technetwork/articles/java/javaserial-1536170.html>

Memory Management

Outgoing Objects

The message transformer will not free objects which have been sent. To release the memory, the application has to explicitly free them when they are no longer used.

Incoming Objects

The message transformer will create an object instance when an object message has been received. To avoid memory leaks, the application must free this instance when it is no longer in use.

Assign a Message Transformer

To insert an object decoder / encoder in the message processing chain, create a message transformer instance and assign it to the connection's `MessageTransformer` property.

The constructor of message transformers for object exchange takes one argument, which is the class of the serialized object. In this example, `SamplePojo` is the class.

Code example

```
Connection: IConnection;
...

with (Connection as IMessageTransformerSupport) do
begin
  MessageTransformer := TBTMessageTransformerXMLOmni.Create(SamplePojo);
end;

...
Connection.Start;
```

You can also use the helper procedure `SetTransformer` in unit `BTConnection`:

Code example

```
Connection: IConnection;
...

SetTransformer(Connection, TBTMessageTransformerXMLOmni.Create(SamplePojo));

...
Connection.Start;
```

Create and Send an ObjectMessage

1. create a `IObjectMessage` instance using `ISession#CreateObjectMessage`

44 Habari Client for RabbitMQ 6.1

2. send the object message to the broker using `IMessageProducer#Send`

Code example

```
ObjectMessage := Session.CreateObjectMessage(Instance);
Producer.Send(ObjectMessage);
```

Complete Example using NativeXml

From `ObjectExchangeTests.pas`.

Send:

Code example

```
procedure TObExTestCase.TestXMLNative;
var
  ObjectMessage: IObjectMessage;
  Obj: SamplePojo;
begin
  // send
  Connection := TBTPConnection.MakeConnection;
  try
    SetTransformer(Connection, TBTPMessageTransformerXMLNative.Create(SamplePojo));
    Connection.Start;
    Session := Connection.CreateSession(False, amAutoAcknowledge);
    Destination := Session.CreateQueue('TOOL.OBJECT.XML');
    Producer := Session.CreateProducer(Destination);
    Obj := SamplePojo.Create;
    try
      Obj.messageText := 'test';
      Obj.messageNo := 0;
      ObjectMessage := Session.CreateObjectMessage(Obj);
      ObjectMessage.SetStringProperty(SH_TRANSFORMATION + '-custom',
        TRANSFORMER_ID_OBJECT_XML); // required for "Delphi Only" object exchange
      Producer.Send(ObjectMessage);
    finally
      Obj.Free;
    end;
  finally
    Connection.Close;
  end;
end;
```

Receive:

Code example

```
Connection := TBTPConnection.MakeConnection;
try
  SetTransformer(Connection, TBTPMessageTransformerXMLNative.Create(SamplePojo));
  Connection.Start;
  Session := Connection.CreateSession(False, amClientAcknowledge);
```

```
Destination := Session.CreateQueue('TOOL.OBJECT.XML');
Consumer := Session.CreateConsumer(Destination);
ObjectMessage := Consumer.Receive(1000) as IObjectMessage;
if Assigned(ObjectMessage) then
begin
    ObjectMessage.Acknowledge;
    Obj := ObjectMessage.GetObject as SamplePojo;
    try
        CheckEquals('test', Obj.messageText);
        CheckEquals(0, Obj.messageNo);
    finally
        Obj.Free;
    end;
end;
finally
    Connection.Close;
end;
end;
```

Stomp 1.2

Connection configuration

A connection string can use additional URL parameters to configure Stomp version 1.1 and 1.2

All parameters can be omitted to use the default value.

Switch	Description	Default
connect.accept-version ²⁰	Supported Stomp versions in ascending order	Broker specific, see below
connect.host ²¹	The name of a virtual host that the client wishes to connect to. It is recommended clients set this to the host name that the socket was established against, or to any name of their choosing. If this header does not match a known virtual host, servers supporting virtual hosting MAY select a default virtual host or reject the connection.	Server URI
connect.heart-beat ²²	Heart beat (outgoing, incoming)	0,0

Default Stomp version (broker-specific)²³

If the connection URL does not contain the connect.accept-version parameter, the client library will add an accept-version header to the CONNECT frame with the value defined in the SH_DEFAULT_STOMP_VERSION constant in the BTBrokerConsts unit.

Default Stomp version			
ActiveMQ	Artemis	OpenMQ	RabbitMQ
1.2	1.2	1.0	1.2

²⁰ http://stomp.github.com/stomp-specification-1.2.html#protocol_negotiation

²¹ http://stomp.github.com/stomp-specification-1.2.html#CONNECT_or_STOMP_Frame

²² <http://stomp.github.com/stomp-specification-1.2.html#Heart-beating>

²³ Since version 5.1 (2017.06)

Connection Factory Code Example:

Code example

```
Factory := TBTConnectionFactory.Create(  
    'stomp://localhost:61613?connect.accept-version=1.2&connect.heart-beat=1000,0');
```

This example creates a connection factory with these connection settings

host: localhost

port: 61613

accept-version: 1.2

heart-beat: 1000,0

- virtual host is localhost
- the client requests Stomp 1.2 protocol
- client heart beat interval is 1000 milliseconds, no server heart beat signals

Specification

For details see the Stomp specification pages:

<http://stomp.github.com//stomp-specification-1.1.html>

<http://stomp.github.com//stomp-specification-1.2.html>

Sending heart-beat signals

A client can use the **SendHeartbeat** method of the connection object to send a heart-beat byte (newline 0x0A).

SendHeartbeat is a method of the IHeartbeat interface, which is declared in the BTSessionIntf unit. A cast of the IConnection object is required to access this method.

Code example

```
(Connection as IHeartbeat).SendHeartbeat;
```

Notes:

48 Habari Client for RabbitMQ 6.1

- the client application code is responsible for sending a heartbeat message within the maximum interval which was specified in the connect parameter – the Habari Client library does not send heart-beats automatically
- client messages which are sent after the heart-beat interval expires may be lost

Checking for incoming heartbeats

The Habari client library stores a time-stamp of the last incoming data. If the time which elapsed since this time-stamp is greater than two times the heart-beat interval, calling **CheckHeartbeat** will raise an exception of type `EBTStompServerHeartbeatMissing`.

Code example

```
(Connection as IHeartbeat).CheckHeartbeat;
```

Notes:

- the method raises an exception if the connection does not use server-side heart-beating
- the method only checks the time elapsed since the last heart-beat, it does not try to read any data from the connection

Reading server-side heartbeats

If the client never needs to consume any messages, but still needs to check for server-side heartbeats, it can use the **ReceiveHeartbeat** method of the connection object.

This method takes one argument, `TimeOut`.

The function returns `True` if it found at least one heart-beat signal on the connection.

Calling `ReceiveHeartbeat` is only useful for applications which never call `Receive`, to check if the server is still healthy, and to consume the pending heart-beat signals from the connection.

If the client reads messages (using `Consumer.Receive`), calling `ReceiveHeartbeat` is not required.

Example Applications

Directory	Description
common	Shared units (see below)
common-consumertool	Receive messages from broker
common-consumertool-fpc	Free Pascal version of ConsumerTool
common-producertool	Send messages to broker
common-producertool-fpc	Free Pascal version of producertool
common-producertool-ssl	Send messages to broker with SSL connection
common-tests	DUnit tests
common-tests-fpc	FPCUnit tests
delphichat	Simple chat client (Delphi 2009)
heartbeat-server	Uses server-side heart-beating to check the connection / server health ²⁴
performance	Multi-threaded performance test application (Delphi 2009)
reconnect	Send messages and reconnect on connection failure
rpc	Use temporary queues to implement request/response style communication (not supported on all message brokers ²⁵)
textmessage	Simple text message example
throughput	Produces and consumes messages continuously
throughput-fpc	Free Pascal version of throughput
transactions	Transaction example
tutorial1	Tutorial one

²⁴ Requires STOMP 1.2; not supported by OpenMQ

²⁵ Not available with ActiveMQ Artemis and HornetQ message broker

Directory	Description
tutorial2	Tutorial two

Table 5: Example Applications (in alphabetic order)

Shared units for demo projects

The directory `demo/common` contains shared units:

- connection configuration form
- command line parameter support class
- LoggingHelper example unit (see “Logging with SLF4P” on page 61)




Illustration 2: Connection configuration dialog example

ConsumerTool

The ConsumerTool demo may be used to receive messages from a queue or topic. This example application is configurable by command line parameters, all are optional.

Parameter	Default Value	Description
AckMode	CLIENT_ACKNOWLEDGE	Acknowledgment mode, possible values are: CLIENT_ACKNOWLEDGE, AUTO_ACKNOWLEDGE or SESSION_TRANSACTED
ClientId		Client Id for durable subscriber
ConsumerName	Habari	name of the message consumer - for durable subscriber
Durable	false	true: use a durable subscriber
MaximumMessages	10	expected number of messages
Password		Password
PauseBeforeShutDown	false	true: wait for key press
ReceiveTimeOut	0	consume messages while they continue to be delivered within the given time out
SleepTime	0	time to sleep after receive
Subject	TOOL.DEFAULT	queue or topic name
Topic	false	true: topic false: queue
Transacted	false	true: transacted session
URL	localhost	server url
User		user name
Verbose	true	verbose output

Table 6: ConsumerTool Command Line Options

```

C:\Users\mj\Desktop\Sandbox\Habari Client libraries\Habari RabbitMQ\demo\c...
Habari Client for RabbitMQ 1.9 (c) 2011-2013 Michael Justin
Connecting to URL: stomp://localhost:61613
Consuming queue: ExampleQueue
Using a non-durable subscription
We are about to wait until we consume: 10 message(s) then we will shutdown
Received: Message: 7 sent at: 08.01.2014 10:35:39      ...
Received: Message: 8 sent at: 08.01.2014 10:35:39      ...
Received: Message: 9 sent at: 08.01.2014 10:35:39      ...
Received: Message: 0 sent at: 08.01.2014 17:11:20      ...
Received: Message: 1 sent at: 08.01.2014 17:11:21      ...
Received: Message: 2 sent at: 08.01.2014 17:11:21      ...
Received: Message: 3 sent at: 08.01.2014 17:11:21      ...
Received: Message: 4 sent at: 08.01.2014 17:11:21      ...
Received: Message: 5 sent at: 08.01.2014 17:11:21      ...
Received: Message: 6 sent at: 08.01.2014 17:11:21      ...
Closing connection

```

Illustration 3: ConsumerTool demo application

Examples

Receive 1000 messages from local broker

```
ConsumerTool --MaximumMessages=1000
```

Receive 10 messages from local broker and wait for any key

```
ConsumerTool --PauseBeforeShutDown
```

Use a transacted session to receive 10,000 messages from local broker

```
ConsumerTool --MaximumMessages=10000 --Transacted --AckMode=SESSION_TRANSACTED
```

ProducerTool

The ProducerTool demo can be used to send messages to the broker. It is configurable by command line parameters, all are optional.

Parameter	Default	Description
MessageCount	10	Number of messages
MessageSize	255	Length of a message in bytes
Persistent	false	Delivery mode 'persistent'
SleepTime	0	Pause between messages in milliseconds
Subject	TOOL.DEFAULT	Destination name
TimeToLive	0	Message expiration time
Topic	false	Destination is a topic
Transacted	false	Use a transaction
URL	localhost	Message broker URL
Verbose	true	Verbose output
User		User name
Password		Password

Table 7: ProducerTool Command Line Options

```

C:\Users\mj\Desktop\Sandbox\Habari Client libraries\Habari RabbitMQ\demo\c...
Habari Client for RabbitMQ 1.9 (c) 2011-2013 Michael Justin
Connecting to URL: stomp://localhost:61613
Publishing a Message with size 255 to queue: ExampleQueue
Using non-persistent messages
Sleeping between publish 0 ms
Sending message: Message: 0 sent at: 10.01.2014 10:49:30
Sending message: Message: 1 sent at: 10.01.2014 10:49:30
Sending message: Message: 2 sent at: 10.01.2014 10:49:30
Sending message: Message: 3 sent at: 10.01.2014 10:49:30
Sending message: Message: 4 sent at: 10.01.2014 10:49:30
Sending message: Message: 5 sent at: 10.01.2014 10:49:30
Sending message: Message: 6 sent at: 10.01.2014 10:49:30
Sending message: Message: 7 sent at: 10.01.2014 10:49:30
Sending message: Message: 8 sent at: 10.01.2014 10:49:30
Sending message: Message: 9 sent at: 10.01.2014 10:49:30
Done.

```

Illustration 4: ProducerTool demo application

Examples

Send 10,000 messages to the queue `TOOL.DEFAULT` on the local broker

54 *Habari Client for RabbitMQ 6.1*

```
ProducerTool --MessageCount 10000
```

Send 10 messages to the topic ExampleTopic on the local broker

```
ProducerTool --Topic --Subject=ExampleTopic
```

Performance test

The performance test application provides a GUI for multi-threaded sending and receiving of messages.

- A broker configuration dialog can be invoked by clicking the URL field
- The communication library (Indy or Synapse) can be selected
- Number and length of messages and thread number can be adjusted using the sliders

For every thread a message queue with the name ExampleQueue.<n> will be used.




Illustration 5: Performance Test Application

Habari Client for RabbitMQ 5.1 includes an enhanced performance test application, which optionally collects message rates of multiple test runs and displays the sample median. Shown above is an example for a client configuration:

56 *Habari Client for RabbitMQ 6.1*

- 21 test runs (triggered by a shift-click on the test button)
- 2000 messages per thread
- 210 bytes payload
- two producer threads, two consumer threads

To start the long-running tests, shift-click on the run button. Taking all test samples takes around ten seconds.

Throughput test

This example application is configurable by command line parameters, all are optional.

Parameter	Default Value	Description
Password	(broker-specific)	Password
Subject	ExampleTopic	Topic name
URL	(broker-specific)	Connection URL
User	(broker-specific)	User name

Table 8: Throughput Test Tool Command Line Options

Examples

Use remote broker 'mybroker' and specify user and password

```
tptest --url=stomp://mybroker --user=test1 --password=secret
```

```

C:\Users\mj\Desktop\Sandbox\Habari Client libraries\Habari Apollo\target\dem...
Habari Client for Apollo 1.6 (c) 2008-2013 Michael Justin
Connecting to URL: stomp://localhost:61613
Consuming: ExampleTopic
Press Ctrl+C to stop
00:02 tx/rx 29213/12152 14562/6057 msgs/sec ( 68/165 microsecs/msg)
00:04 tx/rx 40136/23454 9981/5832 msgs/sec (100/171 microsecs/msg)
00:06 tx/rx 49693/33786 8231/5596 msgs/sec (121/178 microsecs/msg)
00:08 tx/rx 59257/42738 7358/5307 msgs/sec (135/188 microsecs/msg)
00:10 tx/rx 70173/54674 6980/5438 msgs/sec (143/183 microsecs/msg)
00:12 tx/rx 81096/65864 6719/5457 msgs/sec (148/183 microsecs/msg)
00:14 tx/rx 94749/76807 6706/5436 msgs/sec (149/183 microsecs/msg)
00:16 tx/rx 102941/87498 6381/5424 msgs/sec (156/184 microsecs/msg)

```

Illustration 6: Throughput test tool output

Unit Tests

Introduction

Habari Client libraries include DUnit and FPCUnit tests. They require the classic DUnit framework (included in Delphi 2009) or FPCUnit (included in Lazarus 2.6).

The test projects are installed in the common-tests and common-tests-fpc folders.

Test project configuration

Logging

To switch on SLF4P logging, add the conditional symbol `HABARI_LOGGING` (see chapter 'Logging with SLF4P') and rebuild the project. Set the `DEFAULT_LOG_LEVEL` constant in unit `TestHelper` to a valid SLF4P level.

Raw message logging

To switch on raw logging, add the conditional symbol `HABARI_RAW_TRACE` and rebuild the project. The project has the `{$APPTYPE CONSOLE}` flag, which will cause a console window to open.

Optional units

To switch on tests for optional units (object message exchange), add the conditional symbol `TEST_OPTIONAL_UNITS` and rebuild the project.

Synapse communication adapter

To switch from Indy to Synapse for the tests, add the conditional symbol `HABARI_TEST_SYNAPSE` and rebuild the project.

Test units

The common-tests folder contains these units

Test setup and test case base classes	
TestHelper	Main test set-up and utility unit, contains no tests
HabariTestCase	Test case base classes used for for most tests

Unit tests	
ApiTests	Tests Habari Client core API methods – part 1
BasicTests	Tests Habari Client core API methods – part 2
BrokerExtensionsTests	Tests broker-specific features and extensions of the STOMP protocol
HabariExtensionsTests	Tests non-standard features provided by the Habari Client library
HabariTypesTests	Tests internal data types
ObjectExchangeTests ²⁶	Tests object message exchange (for Delphi DUnit only)
Stomp12Tests	Tests features introduced with version 1.2 of the STOMP standard
StubServerTests	Tests using a simple local Stomp server

Free Pascal specific test units are in the folder common-tests-fpc

Test execution

Requirements

The test projects require a message broker running on the local system, which accepts STOMP connections on the default port, with the default user credentials. User name and password for the default user are defined in unit BTBrokerConsts.

Test destinations

Most tests create a test-specific destination (queue or a topic) to reduce the risk of side effects.

The name of the destination is the combination of the test class name and the unit test name.

Note: the unit tests will not clean up or remove these destination objects after usage.

²⁶ only added to the test suite if TEST_OPTIONAL_UNITS is defined

STOMP 1.2

Since Habari Client for RabbitMQ 5.0, the unit test use STOMP 1.2 for connections.

Logging with SLF4P

Introduction

Habari Client libraries include the free open source logging framework SL4FP as an optional dependency.

SLF4P is available at <https://github.com/michaelJustin/slf4p>

IDE and project configuration

In order to compile with SLF4P support,

1. include the path to the slf4p library in the project search or in the global library path
2. add the conditional symbol HABARI_LOGGING to the project options

Delphi

- choose Project | Options... | Delphi Compiler > Conditional defines
- add HABARI_LOGGING

Lazarus

- choose Project | Project Options ... | Compiler Options > Other
- add -dHABARI_LOGGING in the Custom options field

LoggingHelper unit

A simple LoggingHelper unit is located in the demo\common\ directory and can be copied to a project to add slf4p support with little extra coding.

Code example

```
uses
  LoggingHelper,
  ...
begin
```

62 Habari Client for RabbitMQ 6.1

```
// set up logging
LoggingHelper.ConfigureLogging;
```

The `LoggingHelper` unit may be adjusted to your configuration needs. Here is an example which uses the `SimpleLogger` implementation (included in SLF4P).

Code example

```
unit LoggingHelper;

interface

uses
  {$IFDEF HABARI_LOGGING}
  djLogOverSimpleLogger, SimpleLogger
  {$ENDIF HABARI_LOGGING};

const
  DEFAULT_LOG_LEVEL = 'info';

procedure ConfigureLogging(const LogLevel: string = DEFAULT_LOG_LEVEL);

implementation

procedure ConfigureLogging(const LogLevel: string);
begin
  {$IFDEF HABARI_LOGGING}
  SimpleLogger.Configure('defaultLogLevel', LogLevel);
  SimpleLogger.Configure('showDateTime', 'true');
  {$ENDIF HABARI_LOGGING}
end;

end.
```

Conditional Symbols

Caution

All conditional symbols enable experimental or optional features, which are not covered by the free basic support plan. Feedback (suggestions for improvements, feature requests, and bug reports) are always welcome.

Conditional symbols for release builds

HABARI_ALLOW_UNKNOWN_URL_PARAMS

Disables strict connection URL parameter checking.

If this symbol is defined, connection URLs may contain arbitrary parameters. By default, the library only accepts well-known connection parameters and raises an exception for unknown parameters.

Broker versions: all broker versions.

HABARI_LOGGING

Enables logging support. Requires the open source SLF4P logging facade.

Broker versions: all broker versions.

See also: Logging with SLF4P

HABARI_SSL_SUPPORT

Enables SSL support. Support for SSL connections is an advanced / optional feature, technical support is not included in the basic support plan.

The directory source/optional contains example implementations of Indy and Synapse adapter classes with OpenSSL support. Please note that these are basic implementations and not supported in the free basic support plan.

Broker versions: all broker versions.

See also: SSL/TLS Support

HABARI_TCP_KEEPALIVE

Enables configuration option for TCP keep-alive.

For details please see chapter **Connection URL parameters**.

Broker versions: all broker versions.

Indy communication adapter only

HABARI_USE_INTERCEPT

Enables detailed logging of Stomp message frames

This uses the Indy interceptor implementation in unit `IdInterceptSimLog`.

All communication data will be logged to a file. A new file will be created for every new STOMP connection. The file is located in a folder below the current working directory.

If this symbol is defined in a release build, a compiler warning will be emitted:

```
HABARI_USE_INTERCEPT should not be used for release builds
```

Broker versions: all broker versions.

Indy communication adapter only

Note: this feature requires permissions

- create a directory in the current directory if it does not exist
- create files

Conditional symbols for unit test projects

TEST_OPTIONAL_UNITS

Enables tests for experimental / optional units.

HABARI_TEST_SYNAPSE

Enables Synapse communication adapter in DUnit/FPCUnit tests, default is Indy.

Supported for: all versions.

HABARI_TEST_USE_MGMT_API

Enables additional test steps

If this symbol is defined, a broker-specific management client will be instantiated and used in the tests to perform one or more of these actions:

- create destinations on the message broker (test preparation)

- destroy destinations on the message broker (cleanup)
- check destinations for their pending message count

Actual actions depend on the message broker type, see HabariTestCase unit source code for details.

Only available with the DUnit test suite, not for FPCUnit.

Uses SuperObject library (included) and Indy HTTP client

Available since version 5.2.0 (2017.10)

Status: This is work in progress / experimental

Broker versions: Apache ActiveMQ, Apache ActiveMQ Artemis and RabbitMQ. For OpenMQ, a “no op” client will be used to keep the test source code compatible between all broker versions.

SSL/TLS Support

SSL communication adapter classes

Habari Client for RabbitMQ includes two **experimental** adapter classes for usage with OpenSSL, one for Indy (Internet Direct) and one for Synapse. The units for these classes are in the source\optional folder.

Adapter Class	Unit
TBCommAdapterIndySSL	BTCommAdapterIndySSL
TBCommAdapterSynapseSSL	BTCommAdapterSynapseSSL

Table 9: Communication Adapters with SSL Support

Mixed Use

It is possible to use SSL and non-SSL connections in the same project:

- connections with the "stomp://" scheme will remain unencrypted
- connections with the "stomp+ssl://" scheme will use SSL

SSL configuration

The TBCommAdapterIndySSL class includes very basic configuration of the Indy SSL handler. Your server or your specific security requirements may require additional configuration.

Indy SSL Demo

A demo application is included in **common-producertool-ssl**.

Code example

```
program ProducerToolIndySSL;

{$APPTYPE CONSOLE}

uses
```

```
// the Habari Client adapter class for Indy + SSL
BTCommAdapterIndySSL,
// required to set the default adapter
BTAdapterRegistry,
// the common demo unit for the producer tool
ProducerToolUnit in '..\common-producertool\ProducerToolUnit.pas',
// configuration support unit
CommandLineSupport in '..\common\CommandLineSupport.pas',
SysUtils;

begin
  BTAdapterRegistry.SetDefaultAdapter(TBTCommAdapterIndySSL);

  with TProducerTool.Create do
  try
    try
      Run;
    except
      on E:Exception do WriteLn(E.Message);
    end
  finally
    Free;
  end;
  ReadLn;
end.
```

Notes

- the `TBTCommAdapterIndySSL` class must be registered using `(BTAdapterRegistry.SetDefaultAdapter(TBTCommAdapterIndySSL))`
- the project must be compiled with `HABARI_SSL_SUPPORT`
- the connection URL must be in the form `"stomp+ssl://server.com:sslport"`
- the OpenSSL libraries must be in the application search path

Example output

```
Habari Client for RabbitMQ 5.1.0 (c) 2008-2017 Michael Justin
Connecting to URL: stomp+ssl://localhost:61614
Publishing a Message with size 255 to queue: ExampleQueue
Using persistent messages
Sleeping between publish 0 ms
313 INFO habari.TBTCommAdapterIndySSL - Verifying SSL certificate
313 INFO habari.TBTCommAdapterIndySSL - Issuer: /C=GB/ST=Greater Manchester/L=Sa
lford/O=COMODO CA Limited/CN=COMODO RSA Domain Validation Secure Server CA
313 INFO habari.TBTCommAdapterIndySSL - Not After: 09.04.2018 01:59:59
313 INFO habari.TBTCommAdapterIndySSL - Verifying SSL certificate
313 INFO habari.TBTCommAdapterIndySSL - Issuer: /C=GB/ST=Greater Manchester/L=Sa
lford/O=COMODO CA Limited/CN=COMODO RSA Domain Validation Secure Server CA
313 INFO habari.TBTCommAdapterIndySSL - Not After: 09.04.2018 01:59:59
329 INFO habari.TBTStompClient - Connected with RabbitMQ/3.6.10 using STOMP 1.2
Sending message: Message: 0 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 1 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 2 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 3 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 4 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 5 sent at: 28.06.2017 10:26:43      ...
Sending message: Message: 6 sent at: 28.06.2017 10:26:43      ...
```

68 *Habari Client for RabbitMQ 6.1*

```
Sending message: Message: 7 sent at: 28.06.2017 10:26:43    ...  
Sending message: Message: 8 sent at: 28.06.2017 10:26:43    ...  
Sending message: Message: 9 sent at: 28.06.2017 10:26:43    ...  
Done.
```

Support

Support for SSL/TLS connections and the example adapter classes is not included in the basic support package of Habari Client for RabbitMQ.

Useful Units

BTStreamHelper unit

This unit contains the procedure `LoadBytesFromStream` which can be used to read a file into a `BytesMessage`.

Code example

```
// create the message
Msg := Session.CreateBytesMessage;

// open a file
FS := TFileStream.Create('filename.dat', fmOpenRead);

try
  // read the file bytes into the message
  LoadBytesFromStream(Msg, FS);

  Size := Length(Msg.Content);

  // display message content size
  WriteLn(IntToStr(Size) + ' Bytes');

finally
  // release the file stream
  FS.Free;
end;
```

BTJavaPlatform unit

This unit contains some helper functions for Java dates. Java dates are `Int64` values based on the Unix date.

```
function JavaDateToTimeStamp(const JavaDate: Int64): TDateTime;
```

```
function TimeStampToJavaDate(const TimeStamp: TDateTime): Int64;
```

Library Limitations

MessageConsumer

How do I implement synchronous receive from multiple destinations?

The library does not support synchronous receive from more than one destination over a single connection.

To receive messages synchronously (using `Receive` and `ReceiveNoWait`) from two or more destinations, create one connection per destination.

Background: all pending messages in a connection are serialized in one TCP stream, so reading only the messages which come from one of the destinations would require 'skipping' all messages for other destinations.

Message properties

Only string data type supported by Stomp

The STOMP protocol uses string type key/value lists for the representation of message properties. Regardless of the method used to set message properties, all message properties will be interpreted as Java Strings by the Message Broker.

As a side effect, the expressions in a Selector are limited to operations which are valid for strings.

Timestamp properties are converted to a Unix time stamp value, which is the internal representation in Java. But still, these values can not be used with date type expressions.

Broker-specific exceptions

Apache ActiveMQ 5.6 introduced support for numeric expressions in JMS selectors²⁷.

Multi threading

A session supports transactions and it is difficult to implement transactions that are multi-threaded; a session should not be used concurrently by multiple threads.

²⁷ <https://issues.apache.org/jira/browse/AMQ-1609>

Free Pascal specific restrictions

- the library has only been tested on the Windows platform
 - the included unit test project uses FPCUnit for Free Pascal / Lazarus instead of DUnit
 - the third-party libraries for XML and JSON based object exchange do not support Free Pascal
 - the library source code use the Delphi mode switch {\$MODE DELPHI}
 - other limitations or restrictions may apply
-

Broker-specific limitations

Transacted Sessions

Transactional acknowledging

The STOMP implementations of Artemis and OpenMQ message broker do not support transactional acknowledging of incoming messages.

Other broker specific limitations

For broker-specific notes, please read chapter Broker-specific notes.

Frequently Asked Questions

Technical questions

Why am I getting 'undeclared identifier IndyTextEncoding_UTF8'?

Short answer

Your Indy version is too old.

Long answer

The library requires a current Indy 10.6.2 version. Please download a newer Indy version.

Why am I getting 'Found no matching consumer' errors?

Short answer

The client closed a consumer while there still were pending messages on the wire for it, and then tried to receive the pending messages with a new consumer.

Long answer

If the client subscribes to a destination, it creates a unique subscription identifier and passes it to the broker. Messages which the broker sends to the client always include this subscription identifier in their header properties. The client verifies that the subscription id in the incoming message has the same id as the consumer.

If the client closes the consumer before all messages waiting on the wire have been consumed, and creates a new subscription (which has a new unique id), the remaining messages which are waiting on the wire, will have a subscription id which does not match the id of the new subscription. The client will raise an exception if no matching consumer can be found.

Solution

Do not create another consumer on the same connection while there are still pending messages for the first consumer. To discard all pending messages which are still waiting on the wire, the client can simply close the connection and create a new consumer on a new connection.

Example

Here is a small code example which causes this error²⁸:

Code example

```
procedure TErrorHandlingTests.TestReceiveMessageForOtherSubscription;
var
  Factory: IConnectionFactory;
  Conn: IConnection;
  Session: ISession;
  Destination: IDestination;
  Producer: IMessageProducer;
  Consumer: IMessageConsumer;
  Msg: IMessage;
begin
  Factory := TBTConnectionFactory.Create;
  Conn := Factory.CreateConnection;
  Conn.Start;
  Session := Conn.CreateSession(amAutoAcknowledge);
  Destination := Session.CreateQueue(GetQueueName);
  Consumer := Session.CreateConsumer(Destination);
  Producer := Session.CreateProducer(Destination);
  Msg := Session.CreateMessage;
  Producer.Send(Msg);
  Consumer.Close;
  Consumer := Session.CreateConsumer(Destination);
  Consumer.Receive(1000);
end;
```

In line 20 and 21, the consumer is closed and a new consumer created for the same destination.

The Receive in line 22 will detect that the incoming message does not have a matching consumer id and raise an `EIllegalStateException`.

²⁸This code example is included in the library unit test project

Online Resources

Third-party libraries

Internet Direct (Indy)

- Project home <http://www.indyproject.org/>
- Documentation <http://www.indyproject.org/Socket/Docs/index.EN.aspx>
- Installation <http://www.indyproject.org/Socket/Docs/Indy10Installation.EN.aspx>
- Snapshot <https://indy.fulgan.com/ZIP/>
- Subversion <https://svn.atozed.com:444/svn/Indy10/trunk>
- Subversion docs <http://www.indyproject.org/Socket/Download/svn.EN.aspx>

SLF4P

- Project home <https://github.com/michaelJustin/slf4p>
- Git / Subversion <https://github.com/michaelJustin/slf4p.git>

SuperObject

- Project home <https://github.com/hgourvest/superobject>
- Git / Subversion <https://github.com/hgourvest/superobject.git>

Synapse

- Project home <http://synapse.ararat.cz>
- Subversion <https://synalist.svn.sourceforge.net/svnroot/synalist/trunk/>

Specifications

Stomp – Simple (or Streaming) Text Oriented Messaging Protocol²⁹

Stomp home	https://stomp.github.io/index.html
Stomp 1.2	https://stomp.github.io/stomp-specification-1.2.html
Stomp 1.1	https://stomp.github.io/stomp-specification-1.1.html
Stomp 1.0	https://stomp.github.io/stomp-specification-1.0.html

Broker-specific Stomp documentation

ActiveMQ	http://activemq.apache.org/stomp.html
Artemis	http://activemq.apache.org/artemis/docs/1.0.0/interoperability.html
RabbitMQ	https://www.rabbitmq.com/stomp.html

Online articles

Title	Broker
Firebird Database Events and Message-oriented Middleware ³⁰	All
Discover ActiveMQ brokers with Delphi XE4 and Indy 10.6 ³¹	ActiveMQ
Official RabbitMQ Management REST API Documentation ³²	RabbitMQ
How to use the RabbitMQ Web-Stomp Plugin ³³	RabbitMQ
RPC with Delphi client and Java server using RabbitMQ ³⁴	RabbitMQ

²⁹ http://en.wikipedia.org/wiki/Streaming_Text_Oriented_Messaging_Protocol

³⁰ <https://mikejustin.wordpress.com/2012/11/06/firebird-database-events-and-message-oriented-middleware/>

³¹ <https://mikejustin.wordpress.com/2013/07/07/discover-activemq-brokers-with-delphi-xe4-and-indy-10-6/>

³² <https://mikejustin.wordpress.com/2012/10/26/official-rabbitmq-management-rest-api-documentation/>

³³ <https://mikejustin.wordpress.com/2013/11/27/how-to-use-the-rabbitmq-web-stomp-plugin-with-delphi-and-free-pascal/>

³⁴ <https://mikejustin.wordpress.com/2013/05/21/rpc-with-delphi-client-and-java-server-using-rabbitmq/>

Online Videos

Title

Broker

Introduction to Messaging With Apache ActiveMQ³⁵

ActiveMQ

GlassFish Message Queue – High Availability Clusters³⁶

OpenMQ

³⁵ <http://vimeo.com/12654513>

³⁶ <http://www.youtube.com/watch?v=RHUJBSy3udU>

Support

Bug reports and support inquiries

Please send bug reports and support inquiries to cases@habarisoft.com, and specify your message broker type and version.

To allow fast processing of your inquiry, please provide a detailed problem description, including configuration and environment, or code examples which help to reproduce the problem.

Advanced support

Advanced and experimental features such as (for example) SSL, third party libraries, Free Pascal, Linux, non-Unicode Delphi versions and message broker configuration are not covered by the basic support scheme.

Broker-specific notes

Minimum supported broker version

The minimum supported broker version for Habari Client for RabbitMQ 6.1 is RabbitMQ 3.7.3³⁷, which requires Erlang/OTP 19.3 or later.³⁸

The client library does not check the broker version, however client code may check the server version string.³⁹

Online resources

The web page <https://www.rabbitmq.com/stomp.html> documents details of the STOMP implementation in RabbitMQ, including broker-specific extensions.

Note	If you use broker-specific extensions, be aware that moving to a different broker and a different version of Habari Client library later will require more than a simple recompilation of source code
------	---

Message type detection

The library determines the type (binary or text) of incoming STOMP messages based on the **content-type** header. If the header starts with `text/`, the message will be treated as a text message. Otherwise, it will be treated as a binary message (`IBytesMessage`).

Other STOMP clients (for example `node.js`) may be not aware of this RabbitMQ specific rule. If they send a text message without setting content-type to `text/plain`, Habari Client for RabbitMQ will misinterpret them as binary messages.

To fix this, adjust the producer client code to include the content-type header with value `text/plain`.

³⁷ <https://www.rabbitmq.com/changelog.html>

³⁸ for RabbitMQ Erlang Version Requirements see <https://www.rabbitmq.com/which-erlang.html>

³⁹ see `IConnectionInfo.StompServerName`

Prefetch count

The RabbitMQ STOMP documentation explains that

“The prefetch count for all subscriptions is set to unlimited by default. This can be controlled by setting the **prefetch-count** header on SUBSCRIBE frames to the desired integer count.”

With Habari Client for RabbitMQ, the prefetch-count header can be set using a parameter on the destination name for a message consumer:

Code example

```
// create a queue with a prefetch count of 3
Queue := Session.CreateQueue('ExampleQueue?prefetch-count=3');

// create a consumer for this queue
Consumer := Session.CreateConsumer(Queue);

Msg := Consumer.Receive(1000);
```

Destination types

The RabbitMQ STOMP documentation describes five destination types:

- `/exchange` – SEND to arbitrary routing keys and SUBSCRIBE to arbitrary binding patterns;
- `/queue` – SEND and SUBSCRIBE to queues managed by the STOMP gateway;
- `/amq/queue` – SEND and SUBSCRIBE to queues created outside the STOMP gateway;
- `/topic` – SEND and SUBSCRIBE to transient and durable topics;
- `/temp-queue/` – create temporary queues (in reply-to headers only).

Habari Client for RabbitMQ supports all these types: for the special RabbitMQ destination names with `/amq/queue` or `/exchange`, the prefixes can be used in the `Session.CreateTopic` / `Session.CreateQueue` methods.

The prefixes for the three other destination types are added automatically by the library.

Header properties

Habari Client for RabbitMQ does not process these RabbitMQ specific⁴⁰ STOMP headers:

- amqp-message-id** the AMQP message-id property
- content-encoding** the content-encoding property

⁴⁰ <https://www.rabbitmq.com/stomp.html>

Auto-delete queues

The RabbitMQ STOMP plug-in supports advanced queue features, which can be defined in the management interface but also from clients when the queue is created. No matter how these features have been declared, RabbitMQ requires that the client specifies the same feature settings anytime when this queue is used.

If a queue has been created with the auto-delete flag set, the queue is deleted when all consumers have finished using it.⁴¹

Creation of an auto-delete queue

If the queue does not exist yet, it may be created dynamically by subscribing

Code example

```
ClientCallbackQueue := Session.CreateQueue('Callback?auto-delete=true');  
Consumer := Session.CreateConsumer(ClientCallbackQueue);
```

The admin interface will show that the **auto-delete** feature is enabled.

Sending a message to the auto-delete queue

Sending a message to this queue requires to specify that the auto-delete feature is enabled:

Code example

```
Msg := Session.CreateTextMessage;  
Msg.SetStringProperty('auto-delete', 'true');  
Producer.Send(Msg);
```

Queues with x-max-priority

The RabbitMQ STOMP plug-in supports advanced queue features, which can be defined in the management interface but also from clients when the queue is created. No matter how these features have been declared, RabbitMQ requires that the client specifies the same feature settings anytime when this queue is used.

⁴¹ <https://www.rabbitmq.com/amqp-0-9-1-reference.htm>

Creation of the queue

If the queue does not exist yet, it may be created dynamically by subscribing

Code example

```
PriorityQueue := Session.CreateQueue('Priority?x-max-priority=20');  
  
Consumer := Session.CreateConsumer(PriorityQueue);
```

The admin interface will show that the **maximum priority** is 20.

Sending a message to the queue

Sending a message to this queue requires to specify that the maximum priority is 20:

Code example

```
Msg := Session.CreateTextMessage;  
  
Msg.SetIntProperty('x-max-priority', 20);  
  
Producer.Send(Msg);
```

Hint: check the broker log

If your STOMP client code works with special destination features and does not work as expected, always check the RabbitMQ broker log file. On Windows, you may find it in %APPDATA%\RabbitMQ\log. On Unix, it is located in `${install_prefix}/var/log/rabbitmq` ([File Locations documentation](#)).

Temporary queues

RabbitMQ does not support message acknowledge with temporary queues.

To notify about this limitation, Habari Client for RabbitMQ raises an exception when `Msg.Acknowledge` is called on a temporary destination (queue or topic).

Special character encoding in STOMP headers

If a client sends a STOMP header to the RabbitMQ message broker which contains a colon character, the broker will escape it according to the STOMP 1.1 specification as `\c`.

However this happens independent of the STOMP version – even if the library uses STOMP 1.0 for the connection.

The Habari Client for RabbitMQ will not translate this non-standard escape sequence back to the colon character.

82 *Habari Client for RabbitMQ 6.1*

As a workaround, client applications should prefer STOMP 1.2 as this will activate correct escape sequence conversion.

Durable subscriptions with RabbitMQ

Description

If a client needs to receive all the messages published on a topic, including the ones published while the subscriber is inactive, it uses a durable `TopicSubscriber`.

The broker retains a record of this durable subscription and insures that all messages from the topic's publishers are retained until they are acknowledged by this durable subscriber or they have expired.⁴²

In RabbitMQ, the combination of **the topic name and the durable subscriber name** uniquely identifies the durable topic subscription.⁴³

AMQP Semantics

For `SUBSCRIBE` frames, a *shared* queue is created for each distinct subscription ID x destination pair, and bound to the `amq.topic` exchange with routing key `<name>`. A subscription is created against the queue.

After you restart your program and re-subscribe, the broker will know which messages you need that were published while you were away.

Note: if the same combination of topic name and durable subscriber name is used by more than one client, the broker behavior is undefined – messages can be distributed between clients, or one client will receive all messages and other clients never see a message.

Creation

The `ISession` interface contains the `CreateDurableSubscriber` method which creates a durable subscriber to the specified topic.

A durable subscriber `MessageConsumer` is created with a unique durable subscriber name.

Code example

```
// create a durable subscription
Topic := Session.CreateTopic('ExampleTopic');

Consumer := Session.CreateDurableSubscriber(Topic, 'my-subscription-id');
```

42 <https://download.oracle.com/javaee/5/api/javax/jms/TopicSession.html>

43 <https://www.rabbitmq.com/stomp.html>

Deletion

To delete a durable subscriber, RabbitMQ requires that the client first subscribes and then unsubscribes.

Code example

```
// first subscribe, then unsubscribe

Topic := Session.CreateTopic('ExampleTopic');
Session.CreateDurableSubscriber(Topic, 'my-subscription-id');

Session.Unsubscribe(Topic, 'my-subscription-id');
```

Test tool example

With the `ProducerTool` and `ConsumerTool` demo applications, you can send messages to a durable topic:

```
ProducerTool --MessageCount=1000 --Topic --Persistent --Subject=test-durable
```

and receive them from a client:

```
ConsumerTool --MaximumMessages=1000 --Topic --Subject=test-durable --Durable --
ConsumerName=12345 -Verbose
```

Index

Reference

BTBrokerConsts.....	59	IMQProducer.....	9
BTCommAdapterIndy.....	27	Internet Direct (Indy).....	8
BTConnection.....	43	ISession.....	43
Bug reports.....	77	JMSCorrelationID.....	39
CheckHeartbeat.....	48	JMSDeliveryMode.....	39
Conditional symbols for unit test projects	64	JMSExpiration.....	39
Connect.accept-version.....	46	JMSMessageId.....	40
Connect.heart-beat.....	46	JMSPriority.....	39
Connect.host.....	46	JMSReplyTo.....	39f.
Connection.....	28	JMSTimestamp.....	40
Connection URL.....	28	Lazarus.....	8
ConnectionFactory.....	27	Limitations.....	13, 70
ConnectTimeout.....	13	Linux.....	77
ConsumerTool.....	51	Logging.....	61
CreateDurableSubscriber.....	37, 83	LoggingHelper.....	61
CreateObjectMessage.....	43	Message Consumer.....	35
Credentials.....	59	Message Producer.....	35
Destination.....	33	Message properties.....	70
DISCONNECT Receipt.....	26	MessageTransformer.....	43
DUnit.....	8, 58	Multi threading.....	70
EIllegalStateException.....	73	Multiple destinations.....	70
Enables tests for experimental / optional units.....	64	NativeXml.....	42
Experimental features.....	77	Object Message.....	42
Failover Support.....	23	OmniXML.....	42
FPCUnit.....	8, 58	OpenSSL.....	63, 66f.
Free Pascal.....	8	Point-to-point.....	33
HABARI_LOGGING.....	61, 63	ProducerTool.....	53
HABARI_RAW_TRACE.....	11	Programming Model.....	14
HABARI_SSL_SUPPORT.....	63, 67	Publish and subscribe.....	33
HABARI_TCP_KEEPALIVE.....	64	Queue.....	33
HABARI_TEST_SYNAPSE.....	64	Receive.....	36
HABARI_TEST_USE_MGMT_API.....	64	ReceiveHeartbeat.....	48
HABARI_USE_INTERCEPT.....	11, 64	ReceiveNoWait.....	36
HABARI_USE_INTERCEPT.....	11	SamplePojo.....	43
IdInterceptSimLog.....	64	Selector.....	70
IHeartbeat.....	47	Selectors.....	41
IMessageProducer.....	44	SEND Receipt.....	26
IMQConsumer.....	10	SendHeartbeat.....	47
IMQContext.....	9	Session.....	28
		SetDefaultAdapter.....	67
		SetTransformer.....	43

SimpleLogger.....	62	Tcp.keepalive.....	23
SSL.....	77	Test destinations.....	59
Stomp 1.2.....	46	TEST_OPTIONAL_UNITS.....	64
Stomp+ssl.....	66	Throughput test.....	57
Subscribe receipt.....	25	Topic.....	34
SuperObject.....	42	TopicSubscriber.....	37, 83
Support.....	77	Transacted Sessions.....	30, 71
Synapse.....	8 , 13, 58	Transactions.....	70
Synchronous receive.....	70	Unit Tests.....	58
TBTCommAdapterIndySSL.....	66	Virtual host.....	46
TCP.....	70	.receipt.....	26

Table Index

Table 1: Communication Adapters.....	13
Table 2: Failover Transport Options.....	24
Table 3: Session creation parameters.....	30
Table 4: Message Transformer Implementations.....	42
Table 5: Example Applications (in alphabetic order).....	50
Table 6: ConsumerTool Command Line Options.....	51
Table 7: ProducerTool Command Line Options.....	53
Table 8: Throughput Test Tool Command Line Options.....	57
Table 9: Communication Adapters with SSL Support.....	66

Illustration Index

Illustration 1: Programming Model.....	14
Illustration 2: Connection configuration dialog example.....	50
Illustration 3: ConsumerTool demo application.....	51
Illustration 4: ProducerTool demo application.....	53
Illustration 5: Performance Test Application.....	55
Illustration 6: Throughput test tool output.....	57